

Configure remote authentication through RADIUS

Published: 2025-01-29

The ExtraHop system supports Remote Authentication Dial In User Service (RADIUS) for remote authentication and local authorization only. For remote authentication, the ExtraHop system supports unencrypted RADIUS and plaintext formats.

1. Log in to the Administration settings on the ExtraHop system through `https://<extrahop-hostname-or-IP-address>/admin`.
2. In the Access Settings section, click **Remote Authentication**.
3. From the Remote authentication method drop-down menu, select **RADIUS** and then click **Continue**.
4. On the Add RADIUS Server page, type the following information:

Host

The hostname or IP address of the RADIUS server. Make sure that the DNS of the ExtraHop system is properly configured if you specify a hostname.

Secret

The shared secret between the ExtraHop system and the RADIUS server. Contact your RADIUS administrator to obtain the shared secret.

Timeout

The amount of time in seconds that the ExtraHop system waits for a response from the RADIUS server before attempting the connection again.

5. Click **Add Server**.
6. Optional: Add additional servers as needed.
7. Click **Save and Finish**.
8. From the Privilege assignment options drop-down menu, choose one of the following options:
 - **Remote users have full write access**
This option grants remote users full write access to the ExtraHop system. In addition, you can grant additional access for packet downloads, TLS session keys, NDR module access, and NPM module access.
 - **Remote users have full read-only access**
This option grants remote users read-only access to the ExtraHop system. In addition, you can grant additional access for packet downloads, TLS session keys, NDR module access, and NPM module access.
9. Optional: Configure packet and session key access. Select one of the following options to allow remote users to download packet captures and TLS session keys.
 - **No access**
 - **Packet slices only**
 - **Packet headers only**
 - **Packets only**
 - **Packets and session keys**
10. Optional: Configure NDR and NPM module access (On sensors and consoles only).
 - **No access**
 - **Full access**
11. Click **Save and Finish**.
12. Click **Done**.