

Deploy the ExtraHop console in AWS

Published: 2025-01-22

This guide explains how to launch the ExtraHop console AMI to monitor your Amazon Web Services (AWS) environment. You must have administrative access to AWS to launch a third-party AMI and an ExtraHop product key to complete these procedures.

Before you deploy the console, determine the optimal provisioning needs for your environment. For more information, see the [System requirements](#) section.

System requirements

Your environment must meet the following requirements to deploy an ExtraHop console in AWS:

- An AWS account
- Access to the Amazon Machine Image (AMI) of the ExtraHop console
- An ExtraHop console product key
- An AWS instance type that most closely matches the guidelines described in the ExtraHop console Performance Guidelines.

The performance of the virtual ExtraHop console depends on the number of sensors you are deploying in combination with the number of devices you expect the system to discover in your environment. To determine the appropriate sizing, see the [Virtual ExtraHop Console Performance Guidelines](#).

Deployment Size	Recommended Instance Type
Small	c5.xlarge (4 vCPU and 8 GiB RAM)
Medium	c5.2xlarge (8 vCPU and 16 GiB RAM)
Large	c5.4xlarge (16 vCPU and 32 GiB RAM)
Extra Large	c5.9xlarge (36 vCPU and 72 GiB RAM)

Create the ExtraHop instance in AWS

Before you begin

The Amazon Machine Images (AMIs) of the ExtraHop consoles are not publicly shared. Before you can start the deployment procedure, you must send your AWS account ID to your ExtraHop representative. Your account ID will be linked to the ExtraHop AMIs.

1. Sign in to AWS with your username and password.
2. Click **EC2**.
3. In the left navigation panel, under Images, click **AMIs**.
4. Above the table of AMIs, change the **Filter** from **Owned by Me** to **Private Images**.
5. In the **Search AMIs...** field, type ExtraHop.
6. Select the checkbox next to the ExtraHop console AMI, and click **Launch**.
7. On the Choose an Instance Type page, select the instance type that meets the provisioning requirements specified in the [System requirements](#) section above.
8. Click **Next: Configure Instance Details**.
9. Click the **Network** drop-down menu and select one of the VPCs for your organization.
You must launch the ExtraHop console in the same environment as the sensor.
10. Select **Stop** as the default shutdown behavior.

11. Click the **Protect against accidental termination** checkbox.
12. Optional: Click the **IAM role** drop-down menu, and select an IAM role.
13. Optional: If you want to configure two interfaces for VPC, scroll down to the Network Interfaces section and click **Add Device** to associate another interface with your instance.
The default number of network interfaces is one. The two interfaces must be on two different subnets.
14. Click **Next: Add Storage**.
15. Click **Add New Volume**.
 - a) In the **Size (GiB)** field, type a value between 40 and 96, based on the [performance guidelines](#).
 - b) Select **General Purpose SSD (gp3)** from the **Volume Type** drop-down menu.
16. Click **Next: Add Tags**.
17. In the **Value** field, enter a name for the instance.
18. Click **Next: Configure Security Group**.
19. On the Configure Security Group page, follow the procedure below to create a new security group or add ports to an existing group. If you already have a security group with the required ports for ExtraHop, you can skip this step.
 - a) Select either **Create a new Security Group** or **Select an existing security group**. If you choose to edit an existing group, select the group you want to edit. If you choose to create a new group, type a name for the Security group and type a **Description**.
 - b) From the **Type** drop-down menu, select a protocol. Type the port number in the Port Range field.
 - c) For each additional port, click the **Add Rule** button. Then, from the **Type** drop-down menu, select a protocol, and type the port number in the Port Range field.

The following ports and IP addresses must be opened for the ExtraHop AWS instance:

TCP ports 22, 80, and 443 inbound to the console

These ports must be open to download the installer and administer the ExtraHop system.

IP addresses of the sensor that are connected to the console

After the the ExtraHop console is launched, you must modify the security groups of the connected sensors to allow traffic in from the console.
20. Click **Review and Launch**.
21. Scroll down to review the AMI details, instance type, and security group information, and then click **Launch**.
22. In the pop-up window, from the first drop-down menu, select **Proceed without a key pair**.
23. Click the **I acknowledge...** checkbox and then click **Launch Instance**.
24. Click **View Instances** to return to the AWS Management Console.
When you return to the AWS Management Console, you can view your instance on the Initializing screen.

Located under the table, on the **Description** tab, is the IP address or hostname for the console.

Register the ExtraHop system

Complete the following steps to apply your product key and register the system.

If you do not have a product key, contact your ExtraHop account team.



Tip: To verify that your environment can resolve DNS entries for the ExtraHop licensing server, open a terminal application on your Windows, Linux, or macOS client and run the following command:

```
nslookup -type=NS d.extrahop.com
```

If the name resolution is successful, output similar to the following appears:

```
Non-authoritative answer:  
d.extrahop.com nameserver = ns0.use.d.extrahop.com.  
d.extrahop.com nameserver = ns0.usw.d.extrahop.com.
```

1. In your browser, type the IP address of the ExtraHop system (`https://<extrahop_management_ip>`).
2. Review the license agreement, select **I Agree**, and click **Submit**.
3. On the log in screen, type set up for the user name and the instance ID for the password.
You can find the Instance ID on the Description tab of an instance selected on the Initializing screen.
Type the string of characters that follow i- (but not i- itself), and then click **Log In**.
4. Enter your product key, and then click **Register**.