

# ExtraHop Trigger API Reference

Version 5.0.0

© 2015 ExtraHop Networks, Inc. All rights reserved. This manual in whole or in part, may not be reproduced, translated, or reduced to any machine-readable form without prior written approval from ExtraHop Networks, Inc.

Publication Date: 3/11/2016

# Table of Contents

Overview .....	5
Keyboard Shortcuts .....	6
ExtraHop Data Types .....	7
Global Functions .....	8
Classes and Events .....	10
AAA .....	16
ActiveMQ .....	21
AlertRecord .....	23
Application .....	25
Buffer .....	27
CIFS .....	31
Dataset .....	34
DB .....	35
Device .....	39
DHCP .....	41
Discover .....	44
DNS .....	45
FIX .....	48
FLOW .....	51
FTP .....	72
HL7 .....	76
HTTP .....	78
IBMMQ .....	84
ICA .....	88
ICMP .....	92
IPAddress .....	98
Kerberos .....	98
LDAP .....	102
LLDP .....	106

Memcache .....	107
MetricCycle .....	110
MetricRecord .....	111
MongoDB .....	112
MSMQ .....	114
Network .....	118
NFS .....	119
Record .....	121
Remote.HTTP .....	123
Remote.Kafka .....	126
Remote.MongoDB .....	128
Remote.Syslog .....	132
RemoteSyslog .....	134
RTCP .....	135
RTP .....	142
Sampleset .....	145
SDP .....	146
Session .....	148
SIP .....	150
SMPP .....	156
SMTP .....	158
SSL .....	161
Telnet .....	167
Topnset .....	170
Topnset Keys .....	171
TroubleGroup .....	172
Turn .....	173
VLAN .....	174
XML .....	175
Examples .....	175

Example: HTTP Header Object .....	177
Example: SOAP Request .....	179
Example: Customer ID Header .....	180
Example: Database Trigger .....	182
Example: CIFS Trigger .....	184
Example: Memcache Hits and Misses .....	186
Example: Memcache Key Parsing .....	187
Example: Trigger-Based Application Definition .....	190
Example: Session Table .....	192
Example: Create a Custom Trouble Group .....	194
Example: Topnset Key Matching .....	195
Example: Use the Metric Cycle Store .....	196
Example: Device Discovery Notification .....	198
Example: Parse Custom POS Messages with Universal Payload Analysis .....	198
Example: Parse Syslog Over TCP with Universal Payload Analysis .....	200
Example: Send Data to Elasticsearch with Remote.HTTP .....	203
Example: Send Information to Azure Table Service with Remote.HTTP .....	203
Example: Active MQ .....	205

## Overview

Application Inspection triggers are composed of user-defined code that automatically executes on system events through the ExtraHop trigger API. By writing triggers, you can collect custom metric data about the activities on your network. In addition, triggers can perform operations on protocol messages (such as an HTTP request) before the packet is discarded.

The ExtraHop system monitors, extracts, and records a core set of Layer 7 (L7) metrics for devices on the network, such as response counts, error counts, and processing times. After these metrics are recorded for a given L7 protocol, the packets are discarded, freeing resources for continued processing.

Triggers enable you to:

- Generate and store custom metrics to the internal datastore of the ExtraHop system. For example, while the ExtraHop system does not collect information about which user agent generated an HTTP request, you can generate and collect that level of detail by writing a trigger and committing the data to the datastore. You can also view custom data that is stored in the datastore by creating custom metrics pages and displaying those metrics through the Metric Explore and dashboards.
- Generate and sends records to an Explore appliance for long-term storage and retrieval.
- Associate an arbitrary cross-section of monitored traffic with an ExtraHop application container to enable tier-by-tier application-based views as data. Application views augment the device-based views that the ExtraHop system constructs by default.
- Generate custom metrics and send the information to syslog consumers such as Splunk, or to third party databases such as MongoDB or Kafka.
- Initiate a packet capture to record individual flows based on user-specified criteria. You can download captured flows and process them through third-party tools. Your ExtraHop system must be licensed for packet capture to access this feature.

## Keyboard Shortcuts

The following keyboard shortcuts are available in the ExtraHop trigger editor.

### **Control+Space**

This shortcut will bring up the class list for you to select your class. After you select your class, press "." to bring up an auto-complete list.

### **Command+A / Control + A**

This shortcut selects the entire contents of the Trigger Editor window.

### **Shift+Tab**

This shortcut will auto-indent the selected contents of the Trigger Editor window based on the use of curly braces (`{ }`). Select the text you want indented, then press Shift+Tab.

## ExtraHop Data Types

ExtraHop data types record custom metrics using the **Network**, **Application**, and **Device** classes.

The ExtraHop system records data using two key metric categories:

- **Top-level metrics.** Time series of simple data types
  - **count:** Number (e.g., HTTP requests).
  - **snapshot:** A special type of count metric that, when queried over time, returns the most recent value (e.g., TCP established connections).
  - **dataset:** Statistical summary of timing information (5-number summary: min, 25th-percentile, median, 75th-percentile, max).
  - **sampleset:** Statistical summary of timing information (mean and standard deviation).
  - **max:** A special type of count metric that preserves the maximum.
- **Detail metrics.** Time series of data types consisting of key-value pairs, where the key is a string or an IP address and the value is a top-level data type. Detail metrics provide drill-down information for top level metrics.

Examples:

- To record information about the number of HTTP requests over time, use a top-level count metric.
- To record information about HTTP processing time over time, use a top-level sampleset (mean and average) or dataset (5-number summary) metric.
- To record information about the number of times each client IP address accessed the server, use a detail count metric with the IPAddress key and an integer representing the number of accesses as a value.
- To record information about the length of time it took the server to process each URI, use a detail sampleset or dataset metric with the URI string key and an integer representing processing time as a value.
- To record the slowest HTTP statements over time without relying on a **Session** table, use a top-level and a detail max metric.

## Global Functions

Global functions are available to all Trigger API classes.

**commitRecord**(*id*:String, {*key*: value, *key*: value}): void  
Commits a record to the ExtraHop Explore appliance.

**id**: String  
The ID of the type of record type to be created, which cannot begin with a tilde (~).

**fields**: Object  
One or more key-value pairs.

**Note:**The `key` property, or field name, in custom records must adhere to the following requirements:

- `flowID`, `client`, `server`, `sender`, and `receiver` cannot be used as the name of a field.
- `'.`, `:'`, `'['`, and `']'` (period, colon, square brackets) cannot be part of the name of a field.
- `'ex'` cannot be used as the name of a field.

`commitRecord` will raise an exception if any of these conditions are encountered.

**debug**(*message*:String): void  
Writes to the runtime log if debugging is enabled.

**getTimestamp**(): Number (version 4.0.21305+)  
Returns the timestamp from the packet that caused the trigger event to fire, expressed in milliseconds with microseconds as the fractional part after the decimal.

**log**(*message*: String): void  
Writes to the runtime log regardless of whether debugging is enabled or not.

**Note:** The limit for runtime log entries is 2048 bytes. To log larger entries, use `rsyslog`.

**md5**(*message*: String): String  
Returns the MD5 sum of a string.

**sha1**(*message*: String): String  
Returns the sha1 hash of a string.

**uuid**(): String  
Returns a random version 4 Universally Unique Identifier (UUID).

### Deprecated

**exit**(): Void  
Deprecated. Use the `return` statement instead.

**getTimestampMSec**(): Number  
Deprecated. User `getTimestamp` instead.

Multiple calls to `debug` and `log` statements in which the message is the same value will display once every 30 seconds.

You can use local JavaScript functions when you write triggers. Elements in ECMAScript 5 are supported. Examples are:



```
function example(a, b, c) { ... }
```

```
var example = function(a, b, c) { ... }
```

For triggers that contain multiple events (version 3.9.16835+), use the `event` property to see the event on which the trigger is currently executing. For example:

```
if (event === "HTTP_REQUEST") {  
    /* code */  
}  
else if (event === "HTTP_RESPONSE") {  
    /* other code */  
}
```

## Classes and Events

This guide is an API reference for ExtraHop® users writing application inspection triggers™. For more information about creating and using triggers in conjunction with custom pages and applications, refer to [Getting Started with Application Inspection Triggers](#) on the ExtraHop Support Forum.

**Note:** Where applicable in this guide, a firmware revision number is included in parentheses to indicate the firmware revision in which that functionality was introduced.

Class Name	Events	Description
<b>AAA</b>	<b>AAA_REQUEST</b> <b>AAA_RESPONSE</b>	The <b>AAA</b> class allows retrieval of metrics available during the <code>AAA_REQUEST</code> and <code>AAA_RESPONSE</code> events, which fire on every AAA request or response processed by the device.
<b>ActiveMQ</b>	<b>ACTIVEMQ_MESSAGE</b>	The <b>ActiveMQ</b> class allows retrieval of metrics available during the <code>ACTIVEMQ_MESSAGE</code> event, which fire on every Java Message Service (JMS) message processed by the device.
<b>AlertRecord</b>	<b>ALERT_RECORD_COMMIT</b>	The <b>AlertRecord</b> class allows access the current alert information in <code>ALERT_RECORD_COMMIT</code> and fires whenever an alert fires. (version 5.0.0)
<b>Application</b>	N/A	The <b>Application</b> class allows the creation of new applications and adding custom metrics at the application level. Refer to the table in the Application section for a list of events.
<b>Buffer</b>	N/A	A <b>Buffer</b> is an object with the characteristics of an array.
<b>CIFS</b>	<b>CIFS_REQUEST</b> <b>CIFS_RESPONSE</b>	The <b>CIFS</b> class allows retrieval of metrics available during the <code>CIFS_REQUEST</code> and <code>CIFS_RESPONSE</code> events, which fire on every CIFS request or response processed by the device.
<b>Dataset</b>	N/A	The <b>Dataset</b> class is used for representing dataset metrics. It provides access to the raw dataset values and provides an interface for computing percentiles.
<b>DB</b>	<b>DB_REQUEST</b> <b>DB_RESPONSE</b>	The <b>DB</b> class allows retrieval of metrics available during the <code>DB_REQUEST</code> and <code>DB_RESPONSE</code> events, which fire on every DB request or response processed by the device.
<b>Device</b>	N/A	The <b>Device</b> class allows retrieval of device attributes and adding custom metrics at the device level.
<b>DHCP</b>	<b>DHCP_REQUEST</b>	The <b>DHCP</b> class allows the retrieval of metrics available during the <code>DHCP_REQUEST</code> and <code>DHCP_</code>

Class Name	Events	Description
	<b>DHCP_RESPONSE</b>	RESPONSE events, which fire on every DHCP request or response processed by the device. (version 5.0.0)
<b>Discover</b>	<b>NEW_APPLICATION</b> <b>NEW_DEVICE</b> <b>NEW_VLAN</b>	The <b>Discover</b> class provides access to newly discovered VLANs, devices or applications on the NEW_VLAN, NEW_DEVICE, and NEW_APPLICATION events.  NEW_APPLICATION fires every time an application is first discovered.  NEW_DEVICE fires every time a device is first discovered.  NEW_VLAN fires every time a VLAN is first discovered.
<b>DNS</b>	<b>DNS_REQUEST</b> <b>DNS_RESPONSE</b>	The <b>DNS</b> class allows retrieval of metrics available during the DNS_REQUEST and DNS_RESPONSE events, which fire on every DNS request or response processed by the device.
<b>FIX</b>	<b>FIX_REQUEST</b> <b>FIX_RESPONSE</b>	The <b>FIX</b> class allows retrieval of metrics available during the FIX_REQUEST and FIX_RESPONSE events, which fire on every FIX request or response processed by the device.
<b>FLOW</b>	<b>FLOW_CLASSIFY</b> <b>FLOW_RECORD</b> <b>FLOW_TICK</b> <b>FLOW_TURN</b> <b>TCP_CLOSE</b> <b>TCP_OPEN</b> <b>TCP_PAYLOAD</b> <b>UDP_PAYLOAD</b>	<b>Flow</b> refers to a TCP or UDP connection between two endpoints. The Flow class provides access to elements of these conversations, such as endpoint identities and flow age. It also contains a flow store designed to pass objects from request to response on the same flow.  FLOW_CLASSIFY fires every time the L7 protocol of the flow has been determined.  FLOW_RECORD fires every n seconds and whenever a flow closes, after FLOW_CLASSIFY has fired.  FLOW_TICK fires periodically, at a minimum, on every subsequent turn, after FLOW_CLASSIFY has fired.  FLOW_TURN fires on every TCP or UDP turn.  TCP_OPEN fires every time a TCP connection is first established.  TCP_CLOSE every time a TCP connection is shut down.  TCP_PAYLOAD and UDP_PAYLOAD fire every time the payload matches the criteria defined in the associated trigger.

Class Name	Events	Description
<b>FTP</b>	<b>FTP_REQUEST</b> <b>FTP_RESPONSE</b>	The <b>FTP</b> class allows retrieval of metrics available during the <code>FTP_REQUEST</code> and <code>FTP_RESPONSE</code> events, which fire on every FTP request or response processed by the device.
<b>HL7</b>	<b>HL7_REQUEST</b> <b>HL7_RESPONSE</b>	The <b>HL7</b> class allows retrieval of metrics available during the <code>HL7_REQUEST</code> and <code>HL7_RESPONSE</code> events, which fire on every HL7 request or response processed by the device.
<b>HTTP</b>	<b>HTTP_REQUEST</b> <b>HTTP_RESPONSE</b>	The <b>HTTP</b> class allows retrieval of metrics available during the <code>HTTP_REQUEST</code> and <code>HTTP_RESPONSE</code> events, which fire on every HTTP request or response processed by the device.
<b>IBMMQ</b>	<b>IBMMQ_REQUEST</b> <b>IBMMQ_RESPONSE</b>	The <b>IBMMQ</b> class allows retrieval of metrics available during the <code>IBMMQ_REQUEST</code> and <code>IBMMQ_RESPONSE</code> events, which fire on every IBMMQ request or response processed by the device.
<b>ICA</b>	<b>ICA_AUTH</b> <b>ICA_CLOSE</b> <b>ICA_OPEN</b> <b>ICA_TICK</b>	<p>The <b>ICA</b> class allows retrieval of metrics available during the <code>ICA_OPEN</code>, <code>ICA_AUTH</code>, <code>ICA_TICK</code>, and <code>ICA_CLOSE</code> events.</p> <p><code>ICA_AUTH</code> fires every time the ICA authentication is complete.</p> <p><code>ICA_CLOSE</code> fires every time an ICA session is torn down.</p> <p><code>ICA_OPEN</code> fires every time an ICA application first loads.</p> <p><code>ICA_TICK</code> fires periodically while the user interacts with the ICA application.</p>
<b>ICMP</b>	<b>ICMP_MESSAGE</b>	The <b>ICMP</b> class allows retrieval of metrics available during the <code>ICMP_MESSAGE</code> event, which fires on every ICMP message processed by the device.
<b>IPAddress</b>	N/A	The <b>IPAddress</b> class allows setting and retrieval of IP address attributes. <code>IPAddress</code> is the type of IP address properties available on the Flow class.
<b>Kerberos</b>	<b>KERBEROS_REQUEST</b> <b>KERBEROS_RESPONSE</b>	The <b>Kerberos</b> class allows the retrieval of metrics available during the <code>KERBEROS_REQUEST</code> and <code>KERBEROS_RESPONSE</code> events, which fire on every Kerberos request or response processed by the device. (version 5.0.0)
<b>LDAP</b>	<b>LDAP_REQUEST</b> <b>LDAP_RESPONSE</b>	The <b>LDAP</b> class allows retrieval of metrics available during the <code>LDAP_REQUEST</code> and <code>LDAP_RESPONSE</code> events, which fires on every LDAP request or response processed by the

Class Name	Events	Description
		device.
<b>LLDP</b>	<b>LLDP_FRAME</b>	The <b>LLDP</b> class allows retrieval of metrics available during the <code>LLDP_FRAME</code> event, which fires on every LLDP frame processed by the device.
<b>Memcache</b>	<b>MEMCACHE_REQUEST</b> <b>MEMCACHE_RESPONSE</b>	The <b>Memcache</b> class allows retrieval of metrics available during the <code>MEMCACHE_REQUEST</code> and <code>MEMCACHE_RESPONSE</code> events, which fires on every Memcache request or response processed by the device.
<b>MetricCycle</b>	<b>METRIC_CYCLE_BEGIN</b> <b>METRIC_CYCLE_END</b> <b>METRIC_RECORD_COMMIT</b>	The <b>MetricCycle</b> class represents an interval where stats were published. It is valid on the <code>METRIC_CYCLE_BEGIN</code> , <code>METRIC_CYCLE_END</code> , and <code>METRIC_RECORD_COMMIT</code> events.  <code>METRIC_CYCLE_BEGIN</code> fires every time a metric interval begins.  <code>METRIC_CYCLE_END</code> fires every time a metric cycle ends.  <code>METRIC_RECORD_COMMIT</code> fires every time a metric record is committed to the datastore.
<b>MetricRecord</b>	<b>METRIC_RECORD_COMMIT</b>	The <b>MetricRecord</b> class allows access to the current set of metrics in <code>METRIC_RECORD_COMMIT</code> , which fires every time a metric record is committed to the datastore.
<b>MongoDB</b>	<b>MONGODB_REQUEST</b> <b>MONGODB_RESPONSE</b>	The <b>MongoDB</b> class allows retrieval of metrics available during the <code>MONGODB_REQUEST</code> and <code>MONGODB_RESPONSE</code> events, which fires on every MongoDB request or response processed by the device.
<b>MSMQ</b>	<b>MSMQ_MESSAGE</b>	The <b>MSMQ</b> class allows retrieval of metrics available during the <code>MSMQ_MESSAGE</code> event, which fires on every MSMQ user message processed by the device. (version 5.0.0)
<b>Network</b>	N/A	The <b>Network</b> class allows adding custom metrics at the global level.
<b>NFS</b>	<b>NFS_REQUEST</b> <b>NFS_RESPONSE</b>	The <b>NFS</b> class allows retrieval of metrics available during the <code>NFS_REQUEST</code> and <code>NFS_RESPONSE</code> events, which fire on every NFS request or response processed by the device.
<b>Record</b>	N/A	The Record class is used to create a JSON object used to send information to the ExtraHop Explore appliance.
<b>Remote.HTTP</b>	N/A	The <b>Remote.HTTP</b> class allows submission of HTTP REST requests.
<b>Remote.Kafka</b>	N/A	The <b>Remote.Kafka</b> class allows the submission

Class Name	Events	Description
		of messages to a Kafka server. (version 5.0.0)
<b>Remote.MongoDB</b>	N/A	The <b>Remote.MongoDB</b> class allows insertion, removal, and updating of documents in collections in MongoDB.
<b>Remote.Syslog</b>	N/A	The <b>Remote.Syslog</b> class allows creation of remote syslog message with specified content.
<b>RemoteSyslog</b>	N/A	(Deprecated. Use Remote.Syslog instead.) The <b>RemoteSyslog</b> class allows creation of remote syslog messages with specified content.
<b>RTCP</b>	<b>RTCP_MESSAGE</b>	The <b>RTCP</b> class allows for retrieval of metrics available during the <code>RTCP_MESSAGE</code> event, which fires on every RTCP message processed by the device. (version 4.1.22706+)
<b>RTP</b>	<b>RTP_CLOSE</b> <b>RTP_OPEN</b> <b>RTP_TICK</b>	The <b>RTP</b> class allows for retrieval of metrics available during the <code>RTP_CLOSE</code> , <code>RTP_OPEN</code> , and <code>RTP_TICK</code> events.  <code>RTP_CLOSE</code> fires every time RTP connection is closed.  <code>RTP_OPEN</code> fires every time an RTP connection is opened.  <code>RTP_TICK</code> fires periodically on RTP flows.(version 4.1.22706+)
<b>Sampleset</b>	N/A	The <b>Sampleset</b> class is used for representing sampleset metrics.
<b>SDP</b>	<b>SIP_REQUEST</b> <b>SIP_RESPONSE</b>	The <b>SDP</b> class allows for retrieval of Session Description Protocol (SDP) information during the <code>SIP_REQUEST</code> and <code>SIP_RESPONSE</code> events, which fire on every SDP request or response processed by the device.
<b>Session</b>	<b>SESSION_EXPIRE</b>	The <b>Session</b> class allows for manipulation of objects in the global session table, a construct designed for passing objects across flows.
<b>SIP</b>	<b>SIP_REQUEST</b> <b>SIP_RESPONSE</b>	The <b>SIP</b> class allows retrieval of metrics available during the <code>SIP_REQUEST</code> and <code>SIP_RESPONSE</code> events, which fire on every SIP request or response processed by the device. (version 4.1.22706+)
<b>SMPP</b>	<b>SMPP_REQUEST</b> <b>SMPP_RESPONSE</b>	The <b>SMPP</b> class allows retrieval of metrics available during the <code>SMPP_REQUEST</code> and <code>SMPP_RESPONSE</code> events, which fire on every SMPP request or response processed by the device.
<b>SMTP</b>	<b>SMTP_REQUEST</b> <b>SMTP_RESPONSE</b>	The <b>SMTP</b> class allows retrieval of metrics available during the <code>SMTP_REQUEST</code> and <code>SMTP_RESPONSE</code> events, which fire on every

Class Name	Events	Description
		SMTP request or response processed by the device.
<b>SSL</b>	<b>SSL_ALERT</b> <b>SSL_CLOSE</b> <b>SSL_HEARTBEAT</b> <b>SSL_OPEN</b> <b>SSL_PAYLOAD</b> <b>SSL_RECORD</b> <b>SSL_RENEGOTIATE</b>	<p>The <b>SSL</b> class allows retrieval of metrics available during the <code>SSL_ALERT</code>, <code>SSL_CLOSE</code>, <code>SSL_HEARTBEAT</code>, <code>SSL_OPEN</code>, <code>SSL_RECORD</code>, and <code>SSL_RENEGOTIATE</code> events.</p> <p><code>SSL_ALERT</code> fires every time SSL alert is exchanged.</p> <p><code>SSL_CLOSE</code> fires every time an SSL connection is closed.</p> <p><code>SSL_HEARTBEAT</code> fires when every SSL heartbeat message is exchanged.</p> <p><code>SSL_OPEN</code> fires when every SSL connection is first established.</p> <p><code>SSL_PAYLOAD</code> fires when the decrypted SSL payload matches the criteria configured in the associated trigger.</p> <p><code>SSL_RECORD</code> fires when every SSL record is exchanged.</p> <p><code>SSL_RENEGOTIATE</code> fires on every SSL renegotiation.</p>
<b>Telnet</b>	<b>TELNET_MESSAGE</b>	The <b>Telnet</b> class allows retrieval of metrics available during the <code>TELNET_MESSAGE</code> event, which fires on every TELNET command or line of data from the client or the server.
<b>Topnset</b>	N/A	The <b>Topnset</b> class is used for representing topnset metrics. A topnset metric contains a list of entries with keys and values. Values may be numbers, Datasets, Samplesets, or even other Topnsets.
<b>Topnset Keys</b>	N/A	<b>Topnset</b> Keys are objects that represent a property of Topnset.
<b>TroubleGroup</b>	N/A	The <b>TroubleGroup</b> class provides an interface for creating custom trouble groups.
<b>Turn</b>	N/A	The <b>Turn</b> object is a top-level object available in the <code>FLOW_TURN</code> event, which fires on every TCP or UDP turn.
<b>VLAN</b>	N/A	The <b>VLAN</b> class represents a VLAN on the network. It has an <code>id</code> property representing the VLAN ID.
<b>XML</b>	N/A	The <b>XML</b> class allows XML parsing of data.

## AAA

The AAA class allows the retrieval of metrics available during the `AAA_REQUEST` and `AAA_RESPONSE` events.

[Go to \*Classes and Events\*.](#)

### Events

#### **AAA\_REQUEST**

Fires on every AAA request processed by the device.

[Go to \*Classes and Events\*.](#)

#### **AAA\_RESPONSE**

Fires on every AAA response processed by the device.

[Go to \*Classes and Events\*.](#)

### Methods

**commitRecord():** void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

Different properties are returned for the record of `AAA_REQUEST` and `AAA_RESPONSE`. See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**authenticator:** String (version 3.8.16027+)

The value of the authenticator field (RADIUS only).

**avps:** Array

**avpLength:** Number

The size of the AVP, expressed in bytes. This value includes the AVP header data, as well as the value.

**id:** Integer

The numeric ID of the attribute.

**isGrouped:** Boolean

Returns true if this is a grouped AVP (Diameter only).

**name:** String

A string name for the given AVP.

**vendor:** String

The vendor name for vendor AVPs (Diameter only).

**value:** String, Array, or Number

For simple AVPs, a string or numeric value. For grouped AVPs (Diameter only), an array of objects.

**isDiameter:** Boolean

Returns true if the request or response is Diameter.

**isError:** Boolean (`AAA_RESPONSE` only) (version 5.0.0+)

Returns true if the response is an error. To retrieve the error details in Diameter, check `AAA.statusCode`. To retrieve the error details in RADIUS, check the AVP with code 18 (Reply-Message).



**isRadius:** Boolean  
Returns true if the request or response is RADIUS.

**isRspAborted:** Boolean (AAA\_RESPONSE only)  
Returns true if AAA\_RESPONSE is aborted.

**method:** Number  
Corresponds to the command code in either RADIUS or Diameter.

#### Diameter Command Codes

Command Name	Abbr.	Code
AA-Request	AAR	265
AA-Answer	AAA	265
Diameter-EAP-Request	DER	268
Diameter-EAP-Answer	DEA	268
Abort-Session-Request	ASR	274
Abort-Session-Answer	ASA	274
Accounting-Request	ACR	271
Credit-Control-Request	CCR	272
Credit-Control-Answer	CCA	272
Capabilities-Exchange-Request	CER	257
Capabilities-Exchange-Answer	CEA	257
Device-Watchdog-Request	DWR	280
Device-Watchdog-Answer	DWA	280
Disconnect-Peer-Request	DPR	282
Disconnect-Peer-Answer	DPA	282
Re-Auth-Request	RAR	258
Re-Auth-Answer	RAA	258
Session-Termination-Request	STR	275
Session-Termination-Answer	STA	275
User-Authorization-Request	UAR	300
User-Authorization-Answer	UAA	300
Server-Assignment-Request	SAR	301
Server-Assignment-Answer	SAA	301
Location-Info-Request	LIR	302
Location-Info-Answer	LIA	302
Multimedia-Auth-Request	MAR	303
Multimedia-Auth-Answer	MAA	303

Command Name	Abbr.	Code
Registration-Termination-Request	RTR	304
Registration-Termination-Answer	RTA	304
Push-Profile-Request	PPR	305
Push-Profile-Answer	PPA	305
User-Data-Request	UDR	306
User-Data-Answer	UDA	306
Profile-Update-Request	PUR	307
Profile-Update-Answer	PUA	307
Subscribe-Notifications-Request	SNR	308
Subscribe-Notifications-Answer	SNA	308
Push-Notification-Request	PNR	309
Push-Notification-Answer	PNA	309
Bootstrapping-Info-Request	BIR	310
Bootstrapping-Info-Answer	BIA	310
Message-Process-Request	MPR	311
Message-Process-Answer	MPA	311
Update-Location-Request	ULR	316
Update-Location-Answer	ULA	316
Authentication-Information-Request	AIR	318
Authentication-Information-Answer	AIA	318
Notify-Request	NR	323
Notify-Answer	NA	323

### RADIUS Command Codes

Command Name	Code
Access-Request	1
Access-Accept	2
Access-Reject	3
Accounting-Request	4
Accounting-Response	5
Access-Challenge	11
Status-Server (experimental)	12
Status-Client (experimental)	13
Reserved	255

**record:** Object (version 5.0.0)

Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

AAA_REQUEST	AAA_RESPONSE
authenticator	authenticator
method	isError
reqBytes	isRspAborted
reqL2Bytes	method
reqPkts	roundTripTime
reqRTO	rspBytes
txId	rspL2Bytes
	rspPkts
	rspRTO
	statusCode
	tprocess
	txId

**reqBytes:** Number

The number of application-level request bytes.

**reqL2Bytes:** Number

The number of request L2 bytes.

**reqPkts:** Number

The number of request packets.

**reqRTO:** Number (AAA\_REQUEST only)

The number of request RTOs.

**roundTripTime:** Number

The median round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**rspBytes:** Number

The number of application-level response bytes.

**rspL2Bytes:** Number

The number of response L2 bytes.

**rspPkts:** Number

The number of response packets.

**rspRTO:** Number (AAA\_RESPONSE only)

The number of response RTOs.

**statusCode:** String (AAA\_RESPONSE Diameter only)

A string representation of the AVP identifier 268 (Result-Code).

**tprocess:** Number (AAA\_RESPONSE only)

The server processing time, expressed in milliseconds. Will return NaN if the timing is not valid.

**txId:** Number

A value that corresponds to the hop-by-hop identifier in Diameter and `msg-id` in RADIUS.

### Deprecated

**error:** String (`AAA_RESPONSE` only)

Deprecated. Use **isError** instead.

## ActiveMQ

The ActiveMQ class allows the retrieval of metrics available during the `ACTIVEMQ_MESSAGE` event. This is an implementation of the Java Messaging Service (JMS).

*Go to [Classes and Events](#).*

### Events

#### **ACTIVEMQ\_MESSAGE**

Fires on every JMS message processed by the device.

*Go to [Classes and Events](#).*

### Methods

**commitRecord()**: void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**correlationId**: String

The JMSCorrelationID field of the message.

**expiration**: Number

The JMSExpiration field of the message.

**msg: Buffer**

The message body. For `TEXT_MESSAGE` format messages, this returns the body of the message as a UTF-8 string. For all other message formats, this returns the raw bytes.

**msgFormat**: String

The message format. Possible values are:

- BYTES\_MESSAGE
- MAP\_MESSAGE
- MESSAGE
- OBJECT\_MESSAGE
- STREAM\_MESSAGE
- TEXT\_MESSAGE
- BLOG\_MESSAGE

**msgId**: String

The JMSMessageID field of the message.

**totalMsgLength**: Number

The length of the message, expressed in bytes.

**persistent**: Boolean

Returns true if the JMSDeliveryMode is PERSISTENT.

**priority**: Number

The JMSPriority field of the message.

- 0 is the lowest priority.
- 9 is the highest priority.

- 0-4 are gradations of normal priority.
- 5-9 are gradations of expedited priority.

**properties:** Object

Zero or more properties attached to the message. The keys are arbitrary strings and the values may be booleans, numbers, or strings.

**queue:** String

The JMSDestination field of the message.

**receiverBytes:** Number

The number of application-level bytes from the receiver.

**receiverIsBroker:** Boolean

Returns true if the flow-level receiver of the message is a broker.

**receiverL2Bytes:** Number

The number of L2 bytes from the receiver.

**receiverPkts:** Number

The number of packets from the receiver.

**receiverRTO:** Number

The number of RTOs from the receiver.

**record:** Object (version 5.0.0)

Returns an object with all properties appropriately initialized.

The following table shows the properties available.

ACTIVEMQ_MESSAGE
correlationId
expiration
msgFormat
msgId
persistent
priority
queue
receiverBytes
receiverIsBroker
receiverL2Bytes
receiverPkts
receiverRTO
redeliveryCount
replyTo
roundTripTime
senderBytes

ACTIVEMQ_MESSAGE
senderIsBroker
senderL2Bytes
senderPkts
senderRTO
timeStamp
totalMsgLength

**redeliveryCount:** Number  
The number of redeliveries.

**replyTo:** String  
The JMSReplyTo field of the message, converted to a string.

**roundTripTime:** Number  
The median round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**senderBytes:** Number  
The number of application-level bytes from the sender.

**senderIsBroker:** Boolean  
Returns true if the flow-level sender of the message is a broker.

**senderL2Bytes:** Number  
The number of L2 bytes from the sender.

**senderPkts:** Number  
The number of packets from the sender.

**senderRTO:** Number  
The number of RTOs from the sender.

**timeStamp:** Number  
The time when the message was handed off to a provider to be sent, expressed in GMT. This is the JMSTimestamp field of the message.

**totalMsgLength:** Number  
The length of the message, expressed in bytes.

## AlertRecord

(version 5.0.0)

The AlertRecord class allows access the current alert information in `ALERT_RECORD_COMMIT`.

*Go to **Classes and Events**.*

## Events

### ALERT\_RECORD\_COMMIT

Fires when an alert fires. Provides access to information about the alert that has fired.

*Go to **Classes and Events**.*

## Properties

**description:** String

The description of the alert as it appears in the ExtraHop UI.

**id:** String

The ID of the alert record. For example, `extrahop.device.alert`. A list of IDs can be supplied as a hint to the `ALERT_RECORD_COMMIT` event.

**name:** String

The name of the alert that fired.

**object:** Object

The object the alert applies to. For device, application, or VLAN alerts, this property will contain a Device, Application, or VLAN instance, respectively. For capture alerts (e.g., `extrahop.-capture.net`), the property will contain the global Network class.

**time:** Number

The time that the alert record will be published with.



## Application

The Application class allows you to create new applications and add custom metrics at the application level. Applications are user-defined, arbitrary groups of traffic. Applications are defined through triggers only; they cannot be defined in the UI. Application names must use ASCII characters only. Refer to *Getting Started with Application Inspection Triggers* for more information about applications.

Go to [Classes and Events](#).

## Methods

**commit ()**: void

Commits metrics on an application. Applications are automatically created the first time they are referenced. For instance, to create an application named "myApp", use the following syntax:

```
Application("myApp").commit();
```

The application key (e.g., "myApp") must be a string and not an integer. For example, "1020" is treated the same as 1020. Strings that cannot be used include `null` and `Object Object`.

The following table shows which event(s) to use to create applications.

Application Component	Event
AAA	<b>AAA_REQUEST</b> and <b>AAA_RESPONSE</b>
DB	<b>DB_RESPONSE</b>
DNS	<b>DNS_REQUEST</b> and <b>DNS_RESPONSE</b>
FIX	<b>FIX_REQUEST</b> and <b>FIX_RESPONSE</b>
FTP	<b>FTP_RESPONSE</b>
HTTP	<b>HTTP_RESPONSE</b>
IBMMQ	<b>IBMMQ_REQUEST</b> and <b>IBMMQ_RESPONSE</b>
ICA	<b>ICA_TICK</b> and <b>ICA_CLOSE</b>
L4	<b>TCP_OPEN</b> or <b>FLOW_CLASSIFY</b>
LDAP	<b>LDAP_REQUEST</b> and <b>LDAP_RESPONSE</b>
Memcache	<b>MEMCACHE_REQUEST</b> and <b>MEMCACHE_RESPONSE</b>
NAS	<b>CIFS_RESPONSE</b> or <b>NFS_RESPONSE</b>
RTP	<b>RTP_TICK</b>
RTCP	<b>RTCP_MESSAGE</b>
SIP	<b>SIP_REQUEST</b> and <b>SIP_RESPONSE</b>
SSL	<b>SSL_RECORD</b> and <b>SSL_CLOSE</b>
SMTP	<b>SMTP_RESPONSE</b>

**NOTE:** In **TCP\_OPEN** and **FLOW\_CLASSIFY**, `Application.commit` is not valid. Instead use `Flow.setApplication("Report Pools")` to create and assign an L4 application to the

`flow.Flow.setApplication()` can be used from any device event. If you invoke `Application.commit` in an invalid event, the most common error returned will be similar to `"Uncaught Error: Application.commit is not valid on HTTP_REQUEST"`.

Use the following methods to record custom metrics associated with applications. Refer to the **ExtraHop Data Types** section for an overview of the data types.

- **metricAddCount**(*metric\_name*:String, *count*:Number, [*highPrecision*: bool]): void
- **metricAddDataset**(*metric\_name*:String, *val*:Number, [*freq*:Number], [*highPrecision*: bool]): void
- **metricAddDetailCount**(*metric\_name*:String, *key*:String | IPAddress, *count*:Number, [*highPrecision*: bool]): void
- **metricAddDetailSnap**(*metric\_name*:String, *key*:String | IPAddress, *count*:Number, [*highPrecision*: bool]): void
- **metricAddDetailDataset**(*metric\_name*:String, *key*:String | IPAddress, *val*:Number, [*freq*:Number], [*highPrecision*: bool]): void
- **metricAddDetailMax**(*metric\_name*:String, *key*:String | IPAddress, *val*:Number, [*highPrecision*: bool]) void
- **metricAddDetailSampleSet**(*metric\_name*:String, *key*:String | IPAddress, *val*:Number, [*highPrecision*: bool]): void
- **metricAddMax**(*metric\_name*:String, *val*:Number, [*highPrecision*: bool]): void
- **metricAddSampleSet**(*metric\_name*:String, *val*:Number, [*highPrecision*: bool]): void
- **metricAddSnap**(*metric\_name*:String, *count*:Number, [*highPrecision*: bool]): void

The optional `highPrecision` flag will enable one second granularity for the metrics when set to true.

The above methods cannot not be called on `Application` directly, but must be called on specific `Application` instances. For example:

```
Application("myApp").metricAddCount("requests", 1);
Application("myApp").commit();
```

#### Notes:

- When NaN is passed to a `metricAdd*` function, it is silently discarded.
- All count parameters for `metricAdd*` functions only accept a non-zero, positive integer between 1 and  $2^{64}$ .

## Properties

**id**: String (version 4.0.21092+)  
The application ID.

## See Also

- **Example: Trigger-Based Application Definition.**

## Buffer

A buffer is an object with the characteristics of an array. Each element in the array is a number between 0 and 255, representing one byte. It has a length property (the number of items in an array) and a square bracket operator. It contains the `toString()`, `slice()`, `unpack()`, and `decode()` methods.

Encrypted payload is not decrypted for TCP and UDP payload analysis.

`UDP_PAYLOAD` requires a matching string but `TCP_PAYLOAD` does not. If you do not specify a matching string for `TCP_PAYLOAD`, the trigger fires one time after the first *n* bytes of payload.

Go to [Classes and Events](#).

## Methods

**Buffer.decode**(*type*:String): String

Interprets the contents of the Buffer and returns a string with one of the following options:

- utf-8
- ucs2
- hex

**Buffer.toString**(): String

Converts the Buffer to a string.

**Buffer.slice**(*start*: Number, [*end*: Number]): Buffer

Returns the specified bytes in a Buffer as a new Buffer. Bytes are selected starting at the given **start** argument and ending at (but not including) the **end** argument.

**start**: Number

Integer that specifies where to start the selection. Use negative numbers to select from the end of a Buffer. This is zero-based.

**end**: Number

Optional integer that specifies where to end the selection. If omitted, all elements from the start position and to the end of the Buffer will be selected. Use negative numbers to select from the end of a Buffer. This is zero-based.

**Buffer.unpack**(*format*:String, [*offset*:Number]): Array

Processes binary or fixed-width data from any Buffer object, such as one returned by `HTTP.payload`, `Flow.client.payload`, or `Flow.sender.payload`, according to the given format string and, optionally, at the specified offset. The result is a JavaScript array containing unpacked fields, even if it contains exactly one item.

### Notes:

- `Buffer.unpack` uses big-endian, standard alignment, by default.
- The format does not have to consume the entire buffer.
- Null bytes are not included in unpacked strings. For example: `buf.unpack('4s')[0] -> 'example'`.
- The z format character represents variable-length, null-terminated strings. If the last field is z, the string is produced whether or not the null character is present.
- An exception is throw when all of the fields cannot be unpacked because the buffer does not contain enough data.

### Format Strings

Format	C Type	JavaScript Type	Standard Size
x	pad type	no value	
A	struct in6_addr	IPAddress	16
a	struct in_addr	IPAddress	4
b	signed char	string of length 1	1
B	unsigned char	number	1
?	_Bool	boolean	1
h	short	number	2
H	unsigned short	number	2
i	int	number	4
I	unsigned int	number	4
l	long	number	4
L	unsigned long	number	4
q	long long	number	8
Q	unsigned long long	number	8
f	number	number	4
d	double	number	4
s	char[]	string	
z	char[]	string	

The following is an example of a `UDP_PAYLOAD` trigger that parses NTP with `Buffer.unpack`:

```

var buf = Flow.server.payload,
    flags,
    values,
    fmt,
    offset = 0,
    ntpData = {},
    proto = Flow.l7proto;
if ((proto !== 'NTP') || (buf === null)) {
    return;
}

// Parse individual flag values from flags byte
function parseFlags(flags) {
    return {
        'LI': flags >> 6,
        'VN': (flags & 0x3f) >> 3,
        'mode': flags & 0x7
    };
}

```

```
}

// Convert from NTP short format
function ntpShort(n) {
    return n / 65536.0;
}

// Convert integral part of NTP timestamp format to Date
function ntpTimestamp(n) {
    // NTP dates start at 1900, subtract the difference
    // and convert to milliseconds.
    var ms = (n - 0x83aa7e80) * 1000;
    return new Date(ms);
}

// First part of NTP header:
fmt = ('B' + // Flags (LI, VN, mode)
      'B' + // Stratum
      'b' + // Polling interval (signed)
      'b' + // Precision (signed)
      'I' + // Root delay
      'I'); // Root dispersion

values = buf.unpack(fmt);

offset += values.bytes;

flags = parseFlags(values[0]);
if (flags.VN !== 4) {
    // Expecting NTPv4.
    return;
}

ntpData.flags = flags;
ntpData.stratum = values[1];
ntpData.poll = values[2];
ntpData.precision = values[3];
ntpData.rootDelay = ntpShort(values[4]);
ntpData.rootDispersion = ntpShort(values[5]);
// The next field, the reference ID, depends upon the stratum field.
switch (ntpData.stratum)
{
    case 0:
    case 1:
        // Identifier string (4 bytes), and 4 NTP timestamps in two parts
        fmt = '4s8I';
        break;
    default:
        // Unsigned int (based on IP), and 4 NTP timestamps in two parts
```

```
    fmt = 'I8I';  
    break;  
}  
// Passing in offset allows us to continue parsing where we left off.  
values = buf.unpack(fmt, offset);  
ntpData.referenceId = values[0];  
  
// We only use the integral parts of the timestamp here.  
ntpData.referenceTimestamp = ntpTimestamp(values[1]);  
ntpData.originTimestamp = ntpTimestamp(values[3]);  
ntpData.receiveTimestamp = ntpTimestamp(values[5]);  
ntpData.transmitTimestamp = ntpTimestamp(values[7]);  
  
debug('NTP data:' + JSON.stringify(ntpData, null, 4));
```

## Properties

**Buffer.length:** Number

The number of bytes in the Buffer.

**Flow.server.payload:** Buffer

Returns a Buffer containing the server payload. If no payload exists, null is returned.

**Flow.client.payload:** Buffer

Returns a Buffer containing the client payload. If no payload exists, null is returned.

## CIFS

The CIFS class allows the retrieval of metrics available during the `CIFS_REQUEST` and `CIFS_RESPONSE` events.

*Go to [Classes and Events](#).*

### Events

#### **CIFS\_REQUEST**

Fires on every CIFS request processed by the device.

*Go to [Classes and Events](#).*

#### **CIFS\_RESPONSE**

Fires on every CIFS response processed by the device.

*Go to [Classes and Events](#).*

### Method

**commitRecord():** void (`CIFS_RESPONSE` only) (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**accessTime:** Number (`CIFS_RESPONSE` only)

The time it took for the server to access a file on disk, expressed in milliseconds. For CIFS, this is the time from the first READ command in a CIFS flow until the first byte of the payload of its response. Will return NaN if there is no valid measurement, or if the timing is not valid.

**encryptedBytes:** Number (version 5.0.0)

The number of encrypted bytes in the request or response.

**error:** String (`CIFS_RESPONSE` only)

The detailed error message recorded by the ExtraHop system.

**isCommandFileInfo:** Boolean

Returns true if the command is a file info command.

**isCommandLock:** Boolean

Returns true if the command is a locking command.

**isCommandRead:** Boolean

Returns true if the command is a read.

**isCommandWrite:** Boolean

Returns true if the command is a write.

**method:** String

The CIFS method (appears under Methods in the UI).

**record:** Object (`CIFS_RESPONSE` only) (version 5.0.0)

Returns an object with all properties appropriately initialized.

The following table shows the properties available.

CIFS RESPONSE
accessTime
error
isCommandFileInfo
isCommandLock
isCommondRead
isCommandWrite
method
reqBytes
reqL2Bytes
reqPkts
reqRTO
reqSize
resource
roundTripTime
rspBytes
rspL2Bytes
rspPkts
rspRTO
rspSize
share
statusCode
user
warning

**reqBytes:** Number (CIFS\_RESPONSE only)  
The number of L4 request bytes.

**reqL2Bytes:** Number (CIFS\_RESPONSE only)  
The number of L2 request bytes.

**reqPkts:** Number (CIFS\_RESPONSE only)  
The number of request packets.

**reqRTO:** Number (CIFS\_RESPONSE only)  
The number of request RTOs.

**reqSize:** Number  
The size of the request, expressed in bytes.

**resource:** String  
The share, path, and filename, concatenated together.

**roundTripTime:** Number (CIFS\_RESPONSE only)



The median round-trip time (RTT), expressed in milliseconds. May be NaN if there are no RTT samples.

**rspBytes:** Number (CIFS\_RESPONSE only)  
The number of L4 response bytes.

**rspL2Bytes:** Number (CIFS\_RESPONSE only)  
The number of L2 response bytes.

**rspPkts:** Number (CIFS\_RESPONSE only)  
The number of response packets.

**rspRTO:** Number (CIFS\_RESPONSE only)  
The number of response RTOs.

**rspSize:** Number (CIFS\_RESPONSE only)  
The size of the response, expressed in bytes.

**share:** String  
The name of the share to which the user is connected.

**statusCode:** Number (CIFS\_RESPONSE only)  
The numeric status code of the response (SMB2 only).

**user:** String  
The user name, if available. In some cases, such as when the login event was not visible or the access was anonymous, the user name is not available.

**warning:** String (CIFS\_RESPONSE only) (5.0.0+)  
The detailed warning message recorded by the ExtraHop system.

### See Also

- **Example: CIFS Trigger**

## Dataset

The dataset class is used to represent dataset metrics. It provides access to the raw dataset values and provides an interface for computing percentiles.

*Go to [Classes and Events](#).*

### Instance Methods

**percentile(...)**: Array or Number

Accepts a list of percentiles (either as an array or as multiple arguments) to compute and returns the computed percentile values for the dataset. If passed a single numeric argument, a number is returned. Otherwise an array is returned. The arguments must be in ascending order with no duplicates. Floating point values are allowed (e.g., 99.99).

### Instance Properties

**entries**: Array

An array of objects with frequency and value attributes. This is analogous to a frequency table where there is a set of values and the number of times each value was observed.

## DB

The DB class allows the retrieval of metrics available during the `DB_REQUEST` and `DB_RESPONSE` events.

*Go to [Classes and Events](#).*

### Events

#### DB\_REQUEST

Fires on every database request processed by the device.

*Go to [Classes and Events](#).*

#### DB\_RESPONSE

Fires on every database response processed by the device.

*Go to [Classes and Events](#).*

### Method

**commitRecord():** void (`DB_RESPONSE` only) (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**correlationId:** Number (version 4.1.4.24670)

Returns the correlation ID for DB2 applications. Returns NULL for non-DB2 applications.

**database:** String

The database instance. In some cases, such as when login events are encrypted, the database name is not available.

**error:** String (`DB_RESPONSE` only)

The detailed error message(s) recorded by the ExtraHop system in string format. When a database returns multiple errors in one response, `error` will contain a concatenated string of all errors returned.

**errors:** Array of strings (`DB_RESPONSE` only)

The detailed error message(s) recorded by the ExtraHop system in array format. When only a single error is returned, `errors` will contain an array of one string.

**isReqAborted:** Boolean

Returns true if the connection is closed before the DB request is complete.

**isRespAborted:** Boolean (`DB_RESPONSE` only)

Returns true if the connection is closed before the DB response is complete.

**method:** String

Database method (appears under **Methods** in the user interface).

**params:** Array (`DB_REQUEST` only)

List of RPC parameters (only available for Microsoft SQL and DB2 databases). This is an array of objects and each object has the following properties:

**name:** String

The optional name of the supplied RPC parameter and the value is the value of the parameter.

**reqSize:** Number  
The size of the request record at L7, expressed in bytes.

**value:** String | Number  
If the value is not a text, integer, or a time/date field, it will be canonicalized into hex/ASCII form.

**procedure:** String  
The stored procedure name (appears under **Methods** in the user interface).

**record:** Object (`DB_RESPONSE` only) (version 5.0.0)  
Returns an object with all properties appropriately initialized.

The following table shows the properties available.

DB_RESPONSE
correlationId
database
error
isReqAborted
isRspAborted
method
procedure
reqBytes
reqL2Bytes
reqPkts
reqRTO
reqSize
reqTimeToLastByte
roundTripTime
rspBytes
rspL2Bytes
rspPkts
rspRTO
rspSize
rspTimeToFirstByte
rspTimeToLastByte
table
tprocess
user

**reqBytes:** Number (`DB_RESPONSE` only)  
The number of L4 request bytes.

**reqL2Bytes:** Number (DB\_RESPONSE only)  
The number of L2 request bytes.

**reqPkts:** Number (DB\_RESPONSE only)  
The number of request packets.

**reqRTO:** Number (DB\_RESPONSE only)  
The number of request RTOs.

**reqSize:** Number  
The size of the request record at L7, expressed in bytes.

**reqTimeToLastByte:** Number  
The time from the first byte of the request until the last byte of the request, expressed in milliseconds. Will return NaN on malformed and aborted requests, or if the timing is not valid.

**roundTripTime:** Number (DB\_RESPONSE only)  
The median round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**rspBytes:** Number (DB\_RESPONSE only)  
The number of L4 response bytes.

**rspL2Bytes:** Number (DB\_RESPONSE only)  
The number of L2 response bytes.

**rspPkts:** Number (DB\_RESPONSE only)  
The number of response packets.

**rspRTO:** Number (DB\_RESPONSE only)  
The number of response RTOs.

**rspSize:** Number (DB\_RESPONSE only)  
The size of the response record at L7, expressed in bytes.

**rspTimetoFirstByte:** Number (DB\_RESPONSE only)  
The time from the first byte of the request until the first byte of the response, expressed in milliseconds. Will return NaN on malformed and aborted responses, or if the timing is not valid.

**rspTimeToLastByte:** Number (DB\_RESPONSE only)  
The time from the first byte of the request until the last byte of the response, expressed in milliseconds. Will return NaN on malformed and aborted responses, or if the timing is not valid.

**statement:** String (DB\_REQUEST only)  
The full SQL statement (may not be available for all DB methods).

**table:** String (Sybase IQ database only)  
The name of the database table specified in the current statement. This field is empty if there is no table name in the request.

**tprocess:** Number (DB\_RESPONSE only)  
The server processing time, expressed in milliseconds (equivalent to `rspTimeToFirstByte - reqTimeToLastByte`). Will return NaN on malformed and aborted responses, or if the timing is not valid.

**user:** String  
The user name, if available. In some cases, such as when login events are encrypted, the user name is not available.

### See Also

- **Example: Database Trigger**
- **Example: Trigger-Based Application Definition**

## Device

The Device class allows retrieval of device attributes and adding custom metrics at the device level.

[Go to \*Classes and Events\*.](#)

### Instance Methods

The following method is present only on instances of the Device class:

#### Device (id: String)

Constructor for the Device object that accepts one parameter, a unique 16-character string ID. If supplied with an ID from an existing device, the constructor creates a copy of that object with all the properties. Committing metrics on this object with the `metricAdd*` functions will persist them in the datastore. For example:

```
myDevice = new Device(Flow.server.device.id);
debug("myDevice MAC: " + myDevice.hwaddr);
```

Use the following methods to record custom metrics associated with devices. Refer to the ExtraHop Data-types section for an overview of the data types.

- **metricAddCount**(*metric\_name*:String, *count*:Number, [*highPrecision*: bool]): void
- **metricAddDataset**(*metric\_name*:String, *val*:Number, [*freq*:Number], [*highPrecision*: bool]): void
- **metricAddDetailCount**(*metric\_name*:String, *key*:String | IPAddress, *count*:Number, [*highPrecision*: bool]): void
- **metricAddDetailSnap**(*metric\_name*:String, *key*:String | IPAddress, *count*:Number, [*highPrecision*: bool]): void
- **metricAddDetailDataset**(*metric\_name*:String, *key*:String | IPAddress, *val*:Number, [*freq*:Number], [*highPrecision*: bool]): void
- **metricAddDetailMax**(*metric\_name*:String, *key*:String | IPAddress, *val*:Number, [*highPrecision*: bool]) void
- **metricAddDetailSampleSet**(*metric\_name*:String, *key*:String | IPAddress, *val*:Number, [*highPrecision*: bool]): void
- **metricAddMax**(*metric\_name*:String, *val*:Number, [*highPrecision*: bool]): void
- **metricAddSampleSet**(*metric\_name*:String, *val*:Number, [*highPrecision*: bool]): void
- **metricAddSnap**(*metric\_name*:String, *count*:Number, [*highPrecision*: bool]): void

The optional `highPrecision` flag will enable one second granularity for the metrics when set to true.

#### Notes:

- Calling `Device.metricAdd*` functions records metrics for both devices on the flow, regardless of how the triggers are assigned.
- Calling `Flow.client.device.metricAdd*` functions records metrics only for the client device, regardless of whether the trigger is assigned to the client or the server.
- Calling `Flow.server.device.metricAdd*` functions records metrics only for the server device, regardless of whether the trigger is assigned to the client or the server.
- Adding a metric to the Network object makes it available to network-level custom pages.
- Adding a metric to the Device object makes it available to custom pages on that device.

- The `metricAddMax` and `metricAddDetailMax` functions commit metrics that preserve a maximum. For instance, use the `metricAddMax` function to record maximum values of database server processing times overtime.
- If the information is unavailable or not applicable, the value of a property will be null where the type is normally a String and NaN where the type is normally a Number.
- When NaN is passed to a `metricAdd*` function, it is silently discarded.
- All count parameters for `metricAdd*` functions only accept a non-zero, positive integer between 1 and  $2^{64}$ .

## Instance Properties

The following properties allow retrieval of device attributes and are present only on instances of the Device class.

**cdpName:** String

The CDP name associated with the device, if present.

**dhcpName:** String

The DHCP name associated with the device, if present.

**discoverTime:** Number

The last time the capture process discovered the device (not the original discover time), expressed in milliseconds since the epoch (January 1, 1970). Previously discovered devices may be rediscovered by the capture process if they go idle and later become active again, or if the capture process is restarted.

To take trigger action only on the initial discovery of a device, see the **NEW\_DEVICE** trigger event.

**dnsNames:** Array

The DNS names associated with the device, if present.

**hasTrigger:** Boolean

Returns true if the currently executing trigger is configured on the Device object on which the `hasTrigger` property is called. For all trigger events with an associated **FLOW** object, at least one of the Device objects in the flow will have its `hasTrigger` property set to true.

**hwaddr:** String

The MAC address of the device, if present.

**id:** String

The 16-character unique ID of the device, as shown in the ExtraHop UI in the **Device**>> **Device ID** field.

**ipaddrs:** Array

An array of **IPAddress** objects representing the device's known IP addresses. This will always be an array of one IP Address for L3 devices.

**isGateway:** Boolean

Returns true if the device is a gateway.

**isL3:** Boolean (version 4.0.21090+)

Returns true if the device is an L3 device.

**netbiosName:** String

The NetBIOS name associated with the device, if present.

**vlanId:** Number (version 4.0.21091+)



The VLAN ID for the device.

## See Also

- **Example: CIFS Trigger**
- **Example: Customer ID Header**
- **Example: Database Trigger**
- **Example: Device Discovery Notification**
- **Example: HTTP Header Object**
- **Example: Memcache Hits and Misses**
- **Example: Memcache Key Parsing**
- **Example: Parse Custom POS Messages with Universal Payload Analysis**
- **Example: Use the Metric Cycle Store**

## DHCP

The DHCP class allows the retrieval of metrics available during the `DHCP_REQUEST` and `DHCP_RESPONSE` events.

*Go to **Classes and Events**.*

### Events

#### **DHCP\_REQUEST**

Fires on every DHCP request processed by the device.

*Go to **Classes and Events**.*

#### **DHCP\_RESPONSE**

Fires on every DHCP response processed by the device.

*Go to **Classes and Events**.*

### Methods

**commitRecord()**: void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

Different properties are returned for the record of `DHCP_REQUEST` and `DHCP_RESPONSE`. See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

**getOption**(*optionCode*: Integer): Object

Function that takes a DHCP option code as input and returns an object containing the following three fields. If the specified option code is not present in the message, the method return a NULL.

**code**: Number

The DHCP option code.

**name**: String

The DHCP option name.

**payload**: Number | String | IPAddress | Array of IPAddresses | Buffer, etc

The type of payload returned will be whatever the type is for that specific option.

### Properties

**clientAddr**: IPAddress

The IP address of the DHCP client.

**clientReqDelay:** Number (DHCP\_REQUEST only)

The time elapsed before the client attempts to acquire or renew a DHCP lease, expressed in seconds.

**error:** String (DHCP\_RESPONSE only)

The error message associated with option code 56. Will return a NULL if there is no error.

**gwaddr:** IPAddress

The IP address used by routers to relay request and response messages.

**htype:** Number

The hardware type code.

**hwAddr:** IPAddress

The DHCP client hardware address.

**msgType:** String

The DHCP message type. Supported message types are:

- DHCPDISCOVER
- DHCPOFFER
- DHCPREQUEST
- DHCPDECLINE
- DHCPACK
- DHCPNAK
- DHCPRELEASE
- DHCPINFORM
- DHCPFORCERENEW
- DHCPLEASEQUERY
- DHCPLEASEUNASSIGNED
- DHCPLEASEUNKNOWN
- DHCPLEASEACTIVE
- DHCPBULKLEASEQUERY
- DHCPLEASEQUERYDONE

**offeredAddr:** IPAddress (DHCP\_RESPONSE only)

The IP address the DHCP server is offering or assigning to the client.

**options:** Array of Objects

An array of objects with each object containing the following fields:

**code:** Number

The DHCP option code.

**name:** String

The DHCP option name.

**payload:** Number | String | IPAddress | Array of IPAddresses | Buffer, etc

The type of payload returned will be whatever the type is for that specific option.

IP Addresses will be parsed into an array but if the number of bytes is not divisible by 4, it will instead be returned as a Buffer.

**processingTime:** Number (DHCP\_RESPONSE only)

The process time, expressed in milliseconds. Will return NaN on malformed and aborted responses, or if the timing is not valid.

**record:** Object

Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

DHCP_REQUEST	DHCP_RESPONSE
clientReqDelay	msgType
gwAddr	error
hType	gwAddr
msgType	hType
reqBytes	offeredAddr
reqL2Bytes	processingTime
reqPkts	rspBytes
txId	rspL2Bytes
	rspPkts
	txId

**reqBytes:** Number (DHCP\_REQUEST only)  
The number of request bytes.

**reqL2Bytes:** Number (DHCP\_REQUEST only)  
The number of request L2 bytes.

**reqPkts:** Number (DHCP\_REQUEST only)  
The number of request packets.

**rspBytes:** Number (DHCP\_RESPONSE only)  
The number of L4 response bytes.

**rspL2Bytes:** Number (DHCP\_RESPONSE only)  
The number of L2 response bytes.

**rspPkts:** Number (DHCP\_RESPONSE only)  
The number of response packets.

**serverAddr:** IP Address  
The IP address of the server to use for the next step in the bootstrap process.

**txId:** Number  
The transaction ID.

## Discover

The Discover class provides access to newly discovered VLANs, devices, or applications on the `NEW_VLAN`, `NEW_DEVICE`, and `NEW_APPLICATION` events.

*Go to **Classes and Events**.*

## Events

### **NEW\_APPLICATION**

Fires when an application is first discovered.

*Go to **Classes and Events**.*

### **NEW\_DEVICE**

Fires when a device is first discovered.

*Go to **Classes and Events**.*

### **NEW\_VLAN**

Fires when a VLAN is first discovered.

*Go to **Classes and Events**.*

## Properties

**application: Application**(`NEW_APPLICATION` only)

A newly discovered application.

**device: Device**(`NEW_DEVICE` only)

A newly discovered device.

**vlan: VLAN**(`NEW_VLAN` only)

A newly discovered VLAN.

## See Also

- **Example: Device Discovery Notification**

## DNS

The DNS class allows retrieval of metrics available during the `DNS_REQUEST` and `DNS_RESPONSE` events.

[Go to \*Classes and Events\*.](#)

### Events

#### **DNS\_REQUEST**

Fires on every DNS request processed by the device.

[Go to \*Classes and Events\*.](#)

#### **DNS\_RESPONSE**

Fires on every DNS response processed by the device.

[Go to \*Classes and Events\*.](#)

### Methods

**commitRecord():** void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

Different properties are returned for the record of `DNS_REQUEST` and `DNS_RESPONSE`. See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**answers:** Array (`DNS_RESPONSE` only)

An array of objects corresponding to answer resource records. The objects have the following properties:

**data:** String

The value of data depends on the type and will be null for unsupported record types. Supported record types include:

- A
- AAAA
- NS
- PTR
- CNAME
- MX
- SRV
- SOA
- TXT

**name:** String

Record name.

**ttl:** Number

Time-to-live.

**type:** String

DNS record type.

**error:** String (`DNS_RESPONSE` only)

Detailed error message recorded by the ExtraHop system.

**isAuthoritative:** Boolean (`DNS_RESPONSE` only)

Returns true if the authoritative answer is set in the response.

**isReqTimeout:** Boolean (DNS\_REQUEST only)  
Returns true if the request timed out.

**isRspTruncated:** Boolean (DNS\_RESPONSE only)  
Returns true if the response is truncated.

**opcode:** String  
DNS opcode.

#### DNS Opcodes

OpCode	Name
0	Query
1	IQuery (Inverse Query - Obsolete)
2	Status
3	Unassigned
4	Notify
5	Update
6-15	Unassigned

**qname:** String  
Corresponds to the hostname queried.

**qtype:** String  
The DNS request record type.

**record:** Object (version 5.0.0)  
Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

DNS_REQUEST	DNS_RESPONSE
IsReqTimeout	answers
opcode	error
qname	isAuthoritative
qtype	isRspTruncated
reqBytes	opcode
reqL2Bytes	qname
reqPkts	qtype
	rspBytes
	rspL2Bytes
	rspPkts
	tprocess

**reqBytes:** Number (DNS\_REQUEST only)  
The number of application-level request bytes.

**reqL2Bytes:** Number (DNS\_REQUEST only)  
The number of request L2 bytes.

**reqPkts:** Number (DNS\_REQUEST only)  
The number of request packets.

**rspBytes:** Number (DNS\_RESPONSE only)  
The number of response bytes.

**rspL2Bytes:** Number (DNS\_RESPONSE only)  
The number of response L2 bytes.

**rspPkts:** Number (DNS\_RESPONSE only)  
The number of application-level response bytes.

**tprocess:** Number (DNS\_RESPONSE only)  
The server processing time, expressed in milliseconds. Will return NaN on malformed and aborted responses, or if the timing is not valid.

## FIX

The FIX class allows retrieval of metrics available during the `FIX_REQUEST` and `FIX_RESPONSE` events.

[Go to \*Classes and Events\*.](#)

### Events

#### **FIX\_REQUEST**

Fires on every FIX request processed by the device.

[Go to \*Classes and Events\*.](#)

#### **FIX\_RESPONSE**

Fires on every FIX response processed by the device.

[Go to \*Classes and Events\*.](#)

**Note:** `FIX_RESPONSE` is matched with request based on order id. There is no one-to-one correlation between request and response. There could be requests without a response and sometimes data is pushed to the client. That limits request data availability on response event, however the session table could be used to solve any complex scenarios like submission order id, etc.

### Method

**commitRecord():** void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

Different properties are returned for the record of `FIX_REQUEST` and `FIX_RESPONSE`. See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**fields:** Array

A list of FIX fields. Since they are text-based, the key-value protocol fields are exposed as an array of objects with name and value properties containing strings. For example:

```
8=FIX.4.2<SOH>9=233<SOH>35=G<SOH>34=206657...
```

translates to:

```
{"BeginString": "FIX.4.2", "BodyLength": "233", "MsgType": "G", "MsgSeqNum": "206657"}
```

Key string representation is translated, if possible. With extensions, a numeric representation is used. For example, it is not possible to determine `9178=0` (as seen in actual captures). The key is instead translated to `"9178"`. Fields are extracted after message length and version fields are extracted all the way to the checksum (last field). The checksum is not extracted.

For another example, the trigger `debug (JSON.stringify(FIX.fields))`; shows the following fields:



```
[
  {"name": "MsgType", "value": "0"},
  {"name": "MsgSeqNum", "value": "2"},
  {"name": "SenderCompID", "value": "AA"},
  {"name": "SendingTime", "value": "20140904-03:49:58.600"},
  {"name": "TargetCompID", "value": "GG"}
]
```

To debug and print all FIX fields, enable debugging on the trigger and use the following code:

```
var fields = '';
for (var i = 0; i < FIX.fields.length; i++) {
  fields += '"' + FIX.fields[i].name + ' : ' + FIX.fields[i].value +
  '\n';
}
debug(fields);
```

The following output prints to the trigger's Runtime Log:

```
"MsgType" : "5"
"MsgSeqNum" : "3"
"SenderCompID" : "GRAPE"
"SendingTime" : "20140905-00:10:23.814"
"TargetCompID" : "APPLE"
```

**msgType:** String  
The value of the MessageCompID key.

**record:** Object (version 5.0.0)  
Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

FIX_REQUEST	FIX_RESPONSE
msgType	msgType
reqBytes	rspBytes
reqL2Bytes	rspL2Bytes
reqPkts	rspPkts
reqRTO	rspRTO
sender	sender
target	target
version	version

**reqBytes:** Number  
The number of application-level request bytes.

- reqL2Bytes:** Number  
The number of request L2 bytes.
- reqPkts:** Number  
The number of request packets.
- reqRTO:** Number  
The number of request RTOs.
- rspBytes:** Number  
The number of application-level response bytes.
- rspL2Bytes:** Number  
The number of response L2 bytes.
- rspPkts:** Number  
The number of response packets.
- rspRTO:** Number  
The number of response RTOs.
- sender:** String  
The value of the SenderCompID key.
- target:** String  
The value of the TargetCompID key.
- version:** String  
The protocol version.

## FLOW

Flow refers to a TCP or UDP connection between two endpoints. The Flow class provides access to elements of these conversations, such as endpoint identities and flow age. It also contains a flow store designed to pass objects from request to response on the same flow.

Using a combination of L7 payload analysis, observation of TCP handshakes, and port number-based heuristics, the ExtraHop system identifies the L7 protocol and the client and server roles for the endpoints in a flow.

*Go to [Classes and Events](#).*

**NOTE:** Deprecated Flow properties are listed at the end of this section.

### FLOW\_CLASSIFY

Fires once per flow when the L7 protocol of the flow has been determined.

For TCP flows, the `FLOW_CLASSIFY` event fires after the `TCP_OPEN` event.

For certain L7 protocols, the nature of a flow changes over its lifetime (for example, tunneling over HTTP or switching from SMTP to SMTP-TLS). In those cases, `FLOW_CLASSIFY` will fire again after the change.

For flows associated with ExtraHop-monitored protocols (such as HTTP), L7 trigger events (such as `HTTP_REQUEST` and `HTTP_RESPONSE`) will additionally fire for the flow. The Flow object properties and methods discussed in this section are available to every L7 trigger event associated with the flow.

The `FLOW_CLASSIFY` event is useful for initiating an action on a flow when it can be done, based on the earliest knowledge of a flow (for example, client and server IPs, client and server ports, L7 protocol). Actions commonly taken during this trigger event include starting a packet capture via the `captureStart()` method or associating the flow with an application container using `setApplication()`. It is best practice to wait before taking any action until more information becomes known about the flow via a future L7 trigger event (for example, once it's known that the flow is an HTTP request for a specific URI).

*Go to [Classes and Events](#).*

Once the `FLOW_CLASSIFY` trigger event fires, two or more of the following data elements are available, depending on the subsequent trigger event.

Event	Client / Server	Sender / Receiver
AAA_REQUEST	yes	yes
AAA_RESPONSE	yes	yes
ACTIVEMQ_MESSAGE	no	yes
CIFS_REQUEST	yes	yes
CIFS_RESPONSE	yes	yes
DB_REQUEST	yes	yes
DB_RESPONSE	yes	yes
DHCP_REQUEST	yes	yes
DHCP_RESPONSE	yes	yes

Event	Client / Server	Sender / Receiver
DNS_REQUEST	yes	yes
DNS_RESPONSE	yes	yes
HTTP_REQUEST	yes	yes
HTTP_RESPONSE	yes	yes
IBMMQ_REQUEST	yes	yes
IBMMQ_RESPONSE	yes	yes
ICA_AUTH	yes	no
ICA_CLOSE	yes	no
ICA_OPEN	yes	no
ICA_TICK	yes	no
FIX_REQUEST	yes	yes
FIX_RESPONSE	yes	yes
FLOW_CLASSIFY	yes	no
FLOW_TICK	yes	no
FLOW_TURN	yes	no
FTP_REQUEST	yes	yes
FTP_RESPONSE	yes	yes
HL7_REQUEST	yes	yes
HL7_RESPONSE	yes	yes
ICMP_MESSAGE	no	yes
KERBEROS_REQUEST	yes	yes
KERBEROS_RESPONSE	yes	yes
LDAP_REQUEST	yes	yes
LDAP_RESPONSE	yes	yes
MEMCACHE_REQUEST	yes	yes
MEMCACHE_RESPONSE	yes	yes
MONGODB_REQUEST	yes	yes
MONGODB_RESPONSE	yes	yes
MSMQ_MESSAGE	no	yes
NFS_REQUEST	yes	yes
NFS_RESPONSE	yes	yes
RTCP_MESSAGE	no	yes
RTP_CLOSE	no	yes

Event	Client / Server	Sender / Receiver
RTP_OPEN	no	yes
RTP_TICK	no	yes
SIP_REQUEST	yes	yes
SIP_RESPONSE	yes	yes
SMPP_REQUEST	yes	yes
SMPP_RESPONSE	yes	yes
SMTP_REQUEST	yes	yes
SMTP_RESPONSE	yes	yes
SSL_ALERT	yes	yes
SSL_CLOSE	yes	no
SSL_HEARTBEAT	yes	yes
SSL_OPEN	yes	no
SSL_PAYLOAD	yes	yes
SSL_RECORD	yes	yes
SSL_RENEGOTIATE	yes	no
TCP_CLOSE	yes	no
TCP_OPEN	yes	no
TCP_PAYLOAD	yes	yes
UDP_PAYLOAD	yes	yes
TELNET_MESSAGE	yes	yes

## client

### device: Device

The device object associated with the client. For instance, to access the MAC address of the client, use `Flow.client.device.hwaddr`.

### equals: Boolean

Performs an equality test between **Device** and **IPAddress** objects.

### ipaddr: IPAddress

The IP address object associated with the client.

### isAborted: Boolean (version 3.10.18355+)

Returns true if the client has aborted a TCP flow by issuing a TCP reset (RST). This condition may be detected in the `TCP_CLOSE` event and in any impacted L7 events (for example, `HTTP_REQUEST` or `DB_RESPONSE`).

### Notes about aborts:

- An L4 abort occurs when a TCP connection is closed with a RST instead of a graceful shutdown.

- An L7 response abort occurs when a connection closes while in the middle of a response. This can be due to a RST, a graceful FIN shutdown, or an expiration.
- An L7 request abort occurs when a connection closes in the middle of a request. This can also be due to a RST, a graceful FIN shutdown, or an expiration.

**isShutdown:** Boolean (version 4.0.21527+)

Returns true if the client initiated the shutdown of the TCP Connection.

**port:** Number

The port number used by the client in the flow.

## receiver

**device:** Device

The device object associated with the receiver. For instance, to access the MAC address of the receiver, use `Flow.receiver.device.hwaddr`.

**equals:** Boolean

Performs an equality test between **Device** and **IPAddress** objects.

**ipaddr:** IPAddress

The IP address object associated with the receiver.

**isAborted:** Boolean (version 3.10.18355+)

Returns true if the receiver has aborted a TCP flow by issuing a TCP reset (RST). This condition may be detected in the `TCP_CLOSE` event and in any impacted L7 events (for example, `HTTP_REQUEST` or `DB_RESPONSE`).

### Notes about aborts:

- An L4 abort occurs when a TCP connection is closed with a RST instead of a graceful shutdown.
- An L7 response abort occurs when a connection closes while in the middle of a response. This can be due to a RST, a graceful FIN shutdown, or an expiration.
- An L7 request about occurs when a connection closes in the middle of a request. This can also be due to a RST, a graceful FIN shutdown, or an expiration.

**isShutdown:** Boolean (version 4.0.21527+)

Returns true if the receiver initiated the shutdown of the TCP Connection.

**port:** Number

The port number used by the receiver in the flow.

## sender

**device:** Device

The device object associated with the sender. For instance, to access the MAC address of the sender, use `Flow.sender.device.hwaddr`.

**equals:** Boolean

Performs an equality test between **Device** and **IPAddress** objects.

**ipaddr:** IPAddress

The IP address object associated with the sender.

**isAborted:** Boolean (version 3.10.18355+)

Returns true if the sender has aborted a TCP flow by issuing a TCP reset (RST). This condition may be detected in the `TCP_CLOSE` event and in any impacted L7 events (for example, `HTTP_REQUEST` or `DB_RESPONSE`).

**Notes about aborts:**

- An L4 abort occurs when a TCP connection is closed with a RST instead of a graceful shutdown.
- An L7 response abort occurs when a connection closes while in the middle of a response. This can be due to a RST, a graceful FIN shutdown, or an expiration.
- An L7 request about occurs when a connection closes in the middle of a request. This can also be due to a RST, a graceful FIN shutdown, or an expiration.

**isShutdown:** Boolean (version 4.0.21527+)

Returns true if the sender initiated the shutdown of the TCP connection.

**port:** Number

The port number used by the sender in the flow

**server**

**device:** Device

The device object associated with the server. For instance, to access the MAC address of the server, use `Flow.server.device.hwaddr`.

**equals:** Boolean

Performs an equality test between **Device** and **IPAddress** objects.

**ipaddr:** IPAddress

The IP address object associated with the server.

**isAborted:** Boolean (version 3.10.18355+)

Returns true if the server has aborted a TCP flow by issuing a TCP reset (RST). This condition may be detected in the `TCP_CLOSE` event and in any impacted L7 events (for example, `HTTP_REQUEST` or `DB_RESPONSE`).

**Notes about aborts:**

- An L4 abort occurs when a TCP connection is closed with a RST instead of a graceful shutdown.
- An L7 response abort occurs when a connection closes while in the middle of a response. This can be due to a RST, a graceful FIN shutdown, or an expiration.
- An L7 request about occurs when a connection closes in the middle of a request. This can also be due to a RST, a graceful FIN shutdown, or an expiration.

**isShutdown:** Boolean (version 4.0.21527+)

Returns true if the server initiated the shutdown of the TCP connection.

**port:** Number

The port number used by the server in the flow.

By default, the ExtraHop system uses loosely-initiated protocol classification, so it will try to classify flows even after the connection was initiated. Loose initiation can be turned off for ports that do not always carry the protocol traffic (e.g., the wildcard port 0). For such flows, `device1`, `port1`, and `ipaddr1` represent the device with the numerically lower IP address and `device2`, `port2`, and `ipaddr2` represent the device with the numerically higher IP address.

**device1: Device**

The device object associated with the device with a numerically lower IP address. For instance, to access the MAC address of the server, use `Flow.device1.hwaddr`.

**equals:** Boolean

Performs an equality test between device objects.

**device2: Device**

The device object associated with the device with a numerically higher IP address. For instance, to access the MAC address of the server, use `Flow.device2.hwaddr`.

**equals:** Boolean

Performs an equality test between device objects.

**ipaddr1: IPAddress**

The IP address object associated with the device with the numerically lower IP address.

**equals:** Boolean

Performs an equality test between IPAddress objects.

**ipaddr2: IPAddress**

The IP address object associated with the device with the numerically higher IP address.

**equals:** Boolean

Performs an equality test between IPAddress objects.

**port1: Number**

The port number used by the device with the numerically lower IP address.

**port2: Number**

The port number used by the device with the numerically higher IP address.

The following properties and methods apply to both types of flows.

**age: Number**

The time elapsed since the flow was initiated, expressed in seconds.

**captureStart(name:String, [options:Object]): String** (version 3.8.16174+)

Initiates a Precision Packet Capture for the flow and returns a unique identifier of the packet capture (a decimal number as a string). Returns null if the packet capture fails to start.

**name: String**

The name of the packet capture file.

- The maximum length is 256 characters
- The system creates a separate capture for each flow.
- Capture files with the same name are differentiated by timestamps.

**options: Object**

Omit any of the options to indicate unlimited size for that option. "Lookback buffer" refers to packets captured before the call to `captureStart()`. All options apply to the entire flow except the "lookback" options which apply only to the part of the flow before the trigger event that started the packet capture.

**maxBytes: Number**

The total maximum number of bytes.

**maxBytesLookback: Number**

The maximum number of bytes from the lookback buffer.



**MaxDurationMSec:** Number

The maximum duration of the packet capture, expressed in milliseconds. For global packet captures, the default is 1000 milliseconds.

**maxPackets:** Number

The total maximum number of packets.

**maxPacketsLookback:** Number

The maximum number of packets from the lookback buffer.

The following is an example of `Flow.captureStart()`:

```
// EVENT: HTTP_REQUEST
// capture facebook HTTP traffic flows
if (HTTP.uri.indexOf("www.facebook.com") !== -1) {
  var name = "facebook-" + HTTP.uri;
  //packet capture options: capture 20 packets, up to 10 from the
  lookback buffer
  var opts = {
    maxPackets: 20,
    maxPacketsLookback: 10
  };
  Flow.captureStart(name, opts);
}
```

**Notes about capture functionality:**

- The `Flow.captureStart()` function call requires a license with Triggered Packet Capture enabled.
- The packet capture trigger must have packet capture enabled. When configuring the trigger in the Web UI, select the Packet Capture checkbox under Advanced Options.
- Captured files are available in the Admin UI.
- Once the packet capture drive is full, no new captures will be recorded until the user deletes the files manually.
- Maximum file name string length is 256 characters. If the name exceeds 256 characters, it will be truncated and a warning message will be visible in the debug log, but the trigger will continue to execute.
- The capture file size is the lesser of `maxPackets` and `maxBytes`.
- Size of capture allocated to data in the lookback buffer is the lesser of `maxPacketsLookback` and `maxBytesLookback`.
- Each passed `max*` parameter will capture up to the next packet boundary.
- If the packet capture was already started on the current flow, the `Flow.captureStart()` calls result in a warning visible in the debug log, but the trigger will continue to execute.
- There is a maximum of 128 simultaneous packet captures in the system. If that limit is reached, subsequent calls to `Flow.captureStart()` will generate a warning visible in the debug log, but the trigger will continue to execute.

- Packet captures do not include the opening TCP SYN/ACK handshake in versions prior to version 5.0.0. Versions 5.0.0+ include the opening TCP SYN/ACK handshake in packet captures.
- For decrypted flows, `Flow.captureStart()` will still write out the raw packet buffer with encrypted data.

**captureStop():** Boolean (version 3.8.16174+)  
Stops a packet capture that is in progress on the current flow.

**getApplication():** String  
Gets the currently associated application.

**ipproto:** String  
The IP protocol associated with the flow, such as TCP or UDP.

**ipver:** String (version 3.8.16428+)  
The IP version associated with the flow, such as IPv4 or IPv6.

**isExpired:** Boolean  
Returns true if the flow expired at the time of the event.

**l7proto:** String  
The L7 protocol associated with the flow. For known protocols, it is a string representing the protocol name (e.g., HTTP, DB, Memcache, or any L7 section heading in this document). For lesser-known protocols, it is a string with the format `ipproto:port` (e.g., `tcp:13724` or `udp:11258`). Not valid during the `TCP_OPEN` event.

**setApplication(name:String, [turnTiming:Boolean]):** void (version 3.8.16108+)  
Associates L2-L4 metrics for a flow with the L4 component of the application specified by `name`. The `turnTiming` flag is set to `false` by default. If set to `true`, the ExtraHop system collects additional turn timing metrics for the flow. If this flag is omitted, no turn timing metrics are recorded for the application on the associated flow.

`Flow.setApplication(name)` is commonly used in a `FLOW_CLASSIFY` event to associate flows with applications where there is no corresponding L7 trigger event on which to call `Application(name).commit()` (e.g., proprietary protocols for which there is no ExtraHop analysis module). For flows that have L7 trigger events that support the `Application(name).commit()` method, that method collects a larger set of protocol metrics and is generally recommended.

A flow is associated with at most one application at a given instant. It is possible, however, to have a set of triggers call `Flow.setApplication(name)` at different instants and with different `name` arguments over the course of a given flow. This configuration results in metrics for a flow being dispersed across multiple applications and is generally not recommended.

Turn timing analysis analyzes L4 behavior in order to infer L7 processing times when the monitored protocol follows a client-request, server-response pattern and in which the client sends the first message. "Banner" protocols (where the server sends the first message) and protocols where data flows in both directions concurrently are not recommended for turn timing analysis.

**store:** Object

The flow store is designed to pass objects from request to response on the same flow. The `store` object is an instance of an empty JavaScript object. Objects can be attached to the store as properties by defining the property key and property value. For example:

```
Flow.store.myobject = "myvalue";
```

For events that occur on the same flow, you can use `Flow.store` instead of the session table to share information. For example:

```
/* request */
Flow.store.userAgent = HTTP.userAgent;

/* response */
var userAgent = Flow.store.userAgent;
```

**Important:** Flow store values persist across all requests and responses carried on that flow. When working with the flow store, it is a best practice to set the flow store variable to null when its value should not be conveyed to the next request or response. This practice has the added benefit of conserving flow store memory.

Most flow store triggers should have a structure similar to the following example:

```
if (event === 'DB_REQUEST') {
    if (DB.statement) {
        Flow.store.stmt = DB.statement;
    } else {
        Flow.store.stmt = null;
    }
}
else if (event === 'DB_RESPONSE') {
    var stmt = Flow.store.stmt;
    Flow.store.stmt = null;
    if (stmt) {
        // Do something with 'stmt';
        // e.g., commit a metric
    }
}
```

**vlan:** Number

The VLAN number associated with the flow. If no VLAN tag is present, this value is set to 0.

## FLOW\_RECORD

(version 5.0.0+)

Once `FLOW_CLASSIFY` has fired, the `FLOW_RECORD` event will fire every N seconds and whenever a flow closes. The default value for N is 30 seconds.

In addition to the properties and methods given for the `FLOW_CLASSIFY` event, the following properties become available during `FLOW_RECORD` events and the related `FLOW_TICK` and `FLOW_TURN` events. These properties are not available during the `FLOW_CLASSIFY` event.

*Go to **Classes and Events**.*

## Methods

**commitRecord():** void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

## Properties

**Flow.client.record:** Object (version 5.0.0)

Returns an object with all properties appropriately initialized for the client in the flow.

The following table shows the properties available.

FLOW_RECORD
bytes
receiverAddr
receiverPort
first
last
pkts
proto
senderAddr
senderPort
tcpFlags
tos

**Flow.record1:** Object (version 5.0.0)

Returns an object representing traffic sent from the numerically lower IP address in the flow to the numerically higher IP address in the flow.

The following table shows the properties available.

FLOW_RECORD
bytes
receiverAddr
receiverPort
first
last
pkts
proto

FLOW_RECORD
senderAddr
senderPort
tcpFlags
tos

**Flow.record2:** Object (version 5.0.0)

Returns an object representing traffic sent from the numerically higher IP address in the flow to the numerically lower IP address in the flow.

The following table shows the properties available.

FLOW_RECORD
bytes
receiverAddr
receiverPort
first
last
pkts
proto
senderAddr
senderPort
tcpFlags
tos

**Flow.server.record:** Object (version 5.0.0)

Returns an object with all properties appropriately initialized for the server on the flow.

The following table shows the properties available.

FLOW_RECORD
bytes
receiverAddr
receiverPort
first
last
pkts
proto
senderAddr
senderPort
tcpFlags

FLOW_RECORD
tos

## FLOW\_TICK

Once `FLOW_CLASSIFY` has fired, the `FLOW_TICK` event will fire on every subsequent turn. A turn represents a full cycle of a client transferring a response. For turns larger than 128 packets, `FLOW_TICK` will fire every 128 packets. You can configure this threshold in the Admin UI.

`FLOW_TICK` provides a means to periodically check for certain conditions on the flow, such as zero windows and Nagle delays, and then take an action, such as initiating a packet capture or sending a syslog message.

In addition to the properties and methods given for the `FLOW_CLASSIFY` event, the following properties become available during `FLOW_TICK` events and during the related `FLOW_TURN` event. These properties are not available during the `FLOW_CLASSIFY` event.

Go to *Classes and Events*.

### **Flow.bytes1**: Number

The number of L4 payload bytes transmitted by the device with the numerically lower IP address.

### **Flow.bytes2**: Number

The number of L4 payload bytes transmitted by the device with the numerically higher IP address.

### **Flow.dscp1**: Number

The last Differentiated Services Code Point (DSCP) value transmitted by the device with the numerically lower IP address.

### **Flow.dscp2**: Number

The last Differentiated Services Code Point (DSCP) value transmitted by the device with the numerically higher IP address.

### **Flow.l2Bytes1**: Number

The number of L2 bytes, including the ethernet headers, transmitted by the device with the numerically lower IP address.

### **Flow.l2Bytes2**: Number

The number of L2 bytes, including the ethernet headers, transmitted by the device with the numerically higher IP address.

### **Flow.client.customDevices**: Array

A list of custom devices that are acting as the clients in the flow.

### **Flow.client.dscp**: Number

The last Differentiated Services Code Point (DSCP) value transmitted by the client in the flow.

### **Flow.client.dscpBytes**: Array (version 4.1.4.24670)

An array of counts of the number of L2 bytes for a given Differentiated Services Code Point (DSCP) value transmitted by the client in the flow. A zero is returned for each entry which had no bytes of that DSCP value since the last `FLOW_TICK`.

### **Flow.client.dscpPkts**: Array (version 4.1.4.24670)

An array of counts of the number of L2 packets for a given Differentiated Services Code Point (DSCP) value transmitted by the client in the flow. A zero is returned for each entry which had no packets of that DSCP value since the last `FLOW_TICK`.

### **Flow.client.l2Bytes**: Number

The number of L2 bytes, including the ethernet headers, transmitted by the client in the flow.

**Flow.client.nagleDelay:** Number

The number of Nagle delays associated with the client in the flow.

**Flow.client.payload:** Buffer

The payload associated with the client in the flow.

**Flow.client.pkts:** Number

The number of packets transmitted by the client in the flow.

**Flow.client.rcvWndThrottle:** Number

The number of receive window throttles associated with the client in the flow.

**Flow.client.rto:** Number

The number of "RTO Out" when the device is acting as the client in the flow.

**Flow.client.zeroWnd:** Number

The number of zero windows associated with the client in the flow.

**Flow.customDevices1:** Number

A list of custom devices associated with the device with the numerically lower IP address.

**Flow.customDevices2:** Number

A list of custom devices associated with the device with the numerically higher IP address.

**Flow.dscpBytes1:** Array (version 4.1.4.24670)

An array of counts of the number of L2 bytes for a given Differentiated Services Code Point (DSCP) value transmitted by the device with the numerically lower IP address in the flow.

A zero is returned for each entry which had no bytes of that DSCP value since the last FLOW\_TICK.

**Flow.dscpBytes2:** Array (version 4.1.4.24670)

An array of counts of the number of L2 bytes for a given Differentiated Services Code Point (DSCP) value transmitted by the device with the numerically higher IP address in the flow.

A zero is returned for each entry which had no bytes of that DSCP value since the last FLOW\_TICK.

**Flow.dscpPkts1:** Array (version 4.1.4.24670)

An array of counts of the number of L2 packets for a given Differentiated Services Code Point (DSCP) value transmitted by the device with the numerically lower IP address in the flow.

A zero is returned for each entry which had no packets of that DSCP value since the last FLOW\_TICK.

**Flow.dscpPkts2:** Array (version 4.1.4.24670)

An array of counts of the number of L2 packets for a given Differentiated Services Code Point (DSCP) value transmitted by the device with the numerically higher IP address in the flow.

A zero is returned for each entry which had no packets of that DSCP value since the last FLOW\_TICK.

**Flow.nagleDelay1:** Number

The number of nagle delays associated with the device with numerically lower IP address.

**Flow.nagleDelay2:** Number

The number of nagle delays associated with the device with numerically higher IP address.

**Flow.payload1:** Buffer

The payload associated with the device with the numerically lower IP address.

**Flow.payload2:** Buffer

The payload associated with the device with the numerically higher IP address.

**Flow.pkts1:** Number

The number of packets transmitted by the device with the numerically lower IP address.

**Flow.pkts2:** Number

The number of packets transmitted by the device with the numerically higher IP address.

**Flow.rcvWndThrottle1:** Number

The number of times the advertised receive window of the device with the numerically lower IP address limits the throughput of the connection.

**Flow.rcvWndThrottle2:** Number

The number of times the advertised receive window of the device with the numerically higher IP address limits the throughput of the connection.

**Flow.receiver.bytes:** Number

The number of bytes transmitted by the receiver in the flow.

**Flow.receiver.customDevices:** Number

A list of custom devices that are acting as the receivers in the flow.

**Flow.receiver.dscp:** Number

The last Differentiated Services Code Point (DSCP) value transmitted by the receiver in the flow.

**Flow.receiver.dscpBytes:** Array (version 4.1.4.24670)

An array of counts of the number of L2 bytes for a given Differentiated Services Code Point (DSCP) value transmitted by the receiver in the flow. A zero is returned for each entry which had no bytes of that DSCP value since the last FLOW\_TICK.

**Flow.receiver.dscpPkts:** Array (version 4.1.4.24670)

An array of counts of the number of L2 packets for a given Differentiated Services Code Point (DSCP) value transmitted by the receiver in the flow. A zero is returned for each entry which had no packets of that DSCP value since the last FLOW\_TICK.

**Flow.receiver.l2Bytes:** Number

The number of L2 bytes, including the ethernet headers, transmitted by the receiver in the flow.

**Flow.receiver.nagleDelay:** Number

The number of nagle delays associated with the receiver in the flow.

**Flow.receiver.payload:** Buffer

The payload associated with the receiver in the flow. This is always null.

**Flow.receiver.pkts:** Number

The number of packets transmitted by the receiver in the flow.

**Flow.receiver.rcvWndThrottle:** Number

The number of receive window throttles associated with the receiver in the flow.

**Flow.receiver.rto:** Number

The number of "RTO Out" when the device is acting as the receiver in the flow.

**Flow.receiver.zeroWnd:** Number

The number of zero windows associated with the receiver in the flow.

**Flow.roundTripTime:** Number

The median round-trip time (RTT) for the duration of the event, expressed in milliseconds. Will return NaN if there are no RTT samples.



- Flow.rto1:** Number  
The number of RTOs associated with the device with numerically lower IP address.
- Flow.rto2:** Number  
The number of RTOs associated with the device with numerically higher IP address.
- Flow.sender.bytes:** Number  
The number of L4 payload bytes transmitted by the sender in the flow.
- Flow.sender.customDevices:** Number  
A list of custom devices that are acting as the senders in the flow.
- Flow.sender.dscp:** Number  
The last Differentiated Services Code Point (DSCP) value transmitted by the sender in the flow.
- Flow.sender.dscpBytes:** Array (version 4.1.4.24670)  
An array of counts of the number of L2 bytes for a given Differentiated Services Code Point (DSCP) value transmitted by the sender in the flow. A zero is returned for each entry which had no bytes of that DSCP value since the last FLOW\_TICK.
- Flow.sender.dscpPkts:** Array (version 4.1.4.24670)  
An array of counts of the number of L2 packets for a given Differentiated Services Code Point (DSCP) value transmitted by the sender in the flow. A zero is returned for each entry which had no packets of that DSCP value since the last FLOW\_TICK.
- Flow.sender.l2Bytes:** Number  
The number of L2 bytes, including the ethernet headers, transmitted by the sender in the flow.
- Flow.sender.nagleDelay:** Number  
The number of nagle delays associated with the sender in the flow.
- Flow.sender.payload:** Buffer  
The payload associated with the sender in the flow.
- Flow.sender.pkts:** Number  
The number of packets transmitted by the sender in the flow.
- Flow.sender.rcvWndThrottle:** Number  
The number of receive window throttles associated with the sender in the flow.
- Flow.sender.rto:** Number  
The number of "RTO Out" when the device is acting as the sender in the flow.
- Flow.sender.zeroWnd:** Number  
The number of zero windows associated with the sender in the flow.
- Flow.server.bytes:** Number  
The number of L4 payload bytes transmitted by the server in the flow.
- Flow.server.customDevices:** Number  
A list of custom devices that are acting as the servers in the flow.
- Flow.server.dscp:** Number  
The last Differentiated Services Code Point (DSCP) value transmitted by the server in the flow.
- Flow.server.dscpBytes:** Array (version 4.1.4.24670)

An array of counts of the number of L2 bytes for a given Differentiated Services Code Point (DSCP) value transmitted by the server in the flow. A zero is returned for each entry which had no bytes of that DSCP value since the last FLOW\_TICK.

**Flow.server.dscpPkts:** Array (version 4.1.4.24670)

An array of counts of the number of L2 packets for a given Differentiated Services Code Point (DSCP) value transmitted by the server in the flow. A zero is returned for each entry which had no packets of that DSCP value since the last FLOW\_TICK.

**Flow.server.l2Bytes:** Number

The number of L2 bytes transmitted by the server in the flow.

**Flow.server.nagleDelay:** Number

The number of nagle delays associated with the server in the flow.

**Flow.server.payload:** Buffer

The payload associated with the server in the flow.

**Flow.server.pkts:** Number

The number of packets transmitted by the server in the flow.

**Flow.server.rcvWndThrottle:** Number

The number of receive window throttles associated with the server in the flow.

**Flow.server.rto:** Number

The number of "RTO Out" when the device is acting as the server in the flow.

**Flow.server.zeroWnd:** Number

The number of zero windows associated with the server in the flow.

**Flow.zeroWnd1:** Number

The number of zero windows associated with the device with numerically lower IP address.

**Flow.zeroWnd2:** Number

The number of zero windows associated with the device with numerically higher IP address.

The following is an example of FLOW\_TICK:

```
log("RTT " + Flow.roundTripTime);
Remote.Syslog.info(
  " eh_event=FLOW_TICK" +
  " ClientIP="+Flow.client.ipaddr+
  " ServerIP="+Flow.server.ipaddr+
  " ServerPort="+Flow.server.port+
  " ServerName="+Flow.server.device.dnsNames[0]+
  " RTT="+Flow.roundTripTime);
```

## FLOW\_TURN

Fires on every TCP or UDP turn. A turn represents one full cycle of a client transferring request data followed by a server transferring a response.

In addition to the properties of FLOW\_TICK, the event also exposes a Turn object.

*Go to **Classes and Events**.*

## TCP\_CLOSE

Fires when the TCP connection is shut down by being closed, expired or aborted.

*Go to **Classes and Events**.*

**TCP.client.isReset():** Boolean

Returns true if a TCP reset (RST) was seen from the client while the connection was in the process of being shut down.

**TCP.isReset():** Boolean

Returns true if a TCP reset (RST) was seen while the connection was in the process of being shut down.

**TCP.server.isReset():** Boolean

Returns true if a TCP reset (RST) was seen from the server while the connection was in the process of being shut down.

## TCP\_OPEN

Fires when the TCP connection is first fully established. Provides a hook for recording metrics using the following properties:

*Go to **Classes and Events**.*

**TCP.client.getOption():** Array

Returns an array of all TCP options on the client that have a kind number matching the passed in value.

**TCP.client.hasECNEcho:** Boolean

Returns true if the ECN flag is set on the client during the three-way handshake.

**TCP.client.initSeqNum:** Number

The initial sequence number sent from the client during the three-way handshake.

**TCP.client.options:** Array

An array of objects representing the TCP options of the client with a numerically lower IP address in the initial handshake packets. For more information, refer to **TCP Options** below.

**TCP.client.wndSize:** Number

The size of the TCP sliding window on the client negotiated during the three-way handshake.

**TCP.hasECNEcho1:** Boolean

Returns true if the ECN flag is set on the device with a numerically lower IP address during the three-way handshake.

**TCP.hasECNEcho2:** Boolean

Returns true if the ECN flag is set on the device with a numerically higher IP address during the three-way handshake.

**TCP.initSeqNum1:** Number

The initial sequence number of the device with a numerically lower IP address sent during the three-way handshake.

**TCP.initSeqNum2:** Number

The initial sequence number of the device with a numerically higher IP address sent during the three-way handshake.

**TCP.options1:** Array

An array of options representing the TCP options of the device with a numerically lower IP address in the initial handshake packets. For more information, refer to **TCP Options** below.

**TCP.options2:** Array

An array of options representing the TCP options of the device with a numerically higher IP address in the initial handshake packets. For more information, refer to **TCP Options** below.

**TCP.server.getOption()**: Array

Returns an array of all TCP options on the server that have a kind number matching the passed in value.

**TCP.server.hasECNEcho**: Boolean

Returns true if the ECN flag is set on the server during the three-way handshake.

**TCP.server.initSeqNum**: Number

The initial sequence sent from the server during the three-way handshake.

**TCP.server.options**: Array

An array of objects representing the TCP options of the server with a numerically higher IP address in the initial handshake packets. For more information, refer to **TCP Options** below.

**TCP.wndSize1**: Number

The size of the TCP sliding window of the device with a numerically lower IP address negotiated during the three-way handshake.

**TCP.wndSize2**: Number

The size of the TCP sliding window of the device with a numerically higher IP address negotiated during the three-way handshake.

## TCP Options

All TCP Options objects have the following properties:

**kind**: Number

The TCP option kind number.

**TCP Kind Numbers**

Kind No.	Meaning
0	End of Option List
1	No-Operation
2	Maximum Segment Size
3	Window Scale
4	SACK Permitted
5	SACK
6	Echo (obsoleted by option 8)
7	Echo Reply (obsoleted by option 8)
8	Timestamps
9	Partial Order Connection Permitted (obsolete)
10	Partial Order Service Profile (obsolete)
11	CC (obsolete)
12	CC.NEW (obsolete)
13	CC.ECHO (obsolete)

Kind No.	Meaning
14	TCP Alternate Checksum Request (obsolete)
15	TCP Alternate Checksum Data (obsolete)
16	Skeeter
17	Bubba
18	Trailer Checksum Option
19	MD5 Signature Option (obsoleted by option 29)
20	SCPS Capabilities
21	Selective Negative Acknowledgements
22	Record Boundaries
23	Corruption experienced
24	SNAP
25	Unassigned (released 2000-12-18)
26	TCP Compression Filter
27	Quick-Start Response
28	User Timeout Option (also, other known authorized use)
29	TCP Authentication Option (TCP-AO)
30	Multipath TCP (MPTCP)
31	Reserved (known authorized used without proper IANA assignment)
32	Reserved (known authorized used without proper IANA assignment)
33	Reserved (known authorized used without proper IANA assignment)
34	TCP Fast Open Cookie
35-75	Reserved
76	Reserved (known authorized used without proper IANA assignment)
77	Reserved (known authorized used without proper IANA assignment)
78	Reserved (known authorized used without proper IANA assignment)
79-252	Reserved
253	RFC3692-style Experiment 1 (also improperly used for shipping products)
254	RFC3692-style Experiment 2 (also improperly used for shipping products)

**name:** String  
The name of the TCP option.

The following list contains the names of common TCP options and their specific properties:

**Maximum Segment Size** (name 'mss', option kind 2)

**value:** Number  
The maximum segment size.

**Window Scale** (name 'wscale', kind 3)

**value:** Number  
The window scale factor.

**Selective Acknowledgement Permitted** (name 'sack-permitted', kind 4)  
No additional properties. Its presence indicates that the selective acknowledgment option was included in the SYN.

**Timestamp** (name 'timestamp', kind 8)

**tsval:** Number  
The TSVal field for the option.

**tsecr:** Number  
The TSecr field for the option.

**Quickstart Response** (name 'quickstart-rsp', kind 27)

**rate-request:** Number  
The requested rate for transport, expressed in bytes per second.

**ttl-diff:** Number  
The TTLdif.

**qs-nonce:** Number  
The QS Nonce.

**Akamai Address** (name 'akamai-addr', kind 28)

**value:** IPAddr  
The IP Address of the Akamai server.

**User Timeout** (name 'user-timeout', kind 28)

**value:** Number  
The user timeout.

**Authentication** (name 'tcp-ao', kind 29)

**keyId property:** Number  
The key id for the key in use.

**rNextKeyId:** Number  
The key id for the "receive next" key id.

**mac:** Buffer  
The message authentication code.

**Multipath** (name 'mptcp', kind 30)

**value:** Buffer

**Note:** The Akamai Address and User Timeout options are differentiated by the length of the option.

The following is an example using TCP options:

```
if (TCP.client.options != null) {
```

```
var optMSS = TCP.client.getOption(2)

if (optMSS && (optMSS.value > 1460)) {
  Network.metricAddCount('large_mss', 1);
  Network.metricAddDetailCount('large_mss_by_client_ip',
    Flow.client.ipaddr + " " +
    optMSS.value, 1);
}

}
```

### TCP\_PAYLOAD

Fires when the payload matches the criteria configured in the associated trigger.

*Go to **Classes and Events**.*

### UDP\_PAYLOAD

Fires when the payload matches the criteria configured in the associated trigger.

*Go to **Classes and Events**.*

### Deprecated

**Flow.isClientAborted:** Boolean (version 3.10.18355+)  
Deprecated. Use `Flow.client.isAborted` instead.

**Flow.isServerAborted:** Boolean (version 3.10.18355+)  
Deprecated. Use `Flow.server.isAborted` instead.

**Flow.turnInfo:** String (version 3.9.17624+)  
Deprecated. Use the top-level Turn object with attributes for the turn.

### See Also

- **Example: CIFS Trigger**
- **Example: Customer ID Header**
- **Example: Database Trigger**
- **Example: Parse Custom POS Messages with Universal Payload Analysis**
- **Example: Parse Syslog Over TCP with Universal Payload Analysis**
- **Example: SOAP Request**

## FTP

(version 4.0.18766+)

The FTP class allows retrieval of metrics available during the `FTP_REQUEST` and `FTP_RESPONSE` events.

*Go to [Classes and Events](#).*

### Events

#### FTP\_REQUEST

Fires on every FTP request processed by the device.

*Go to [Classes and Events](#).*

#### FTP\_RESPONSE

Fires on every FTP response processed by the device.

*Go to [Classes and Events](#).*

### Method

**commitRecord():** void (`FTP_RESPONSE` only) (version 5.0.0)  
Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**args:** String (`FTP_RESPONSE` only)  
The arguments to the command.

**cwd:** String (`FTP_RESPONSE` only)  
In the case of a user at /, when the client sends "CWD subdir":

- FTP.cwd will be / when `method == "CWD"`.
- FTP.cwd will be /subdir for subsequent commands (rather than CWD becoming the changed to directory as part of the CWD response trigger).

Includes "..." at the beginning of the path in the event of a resync or the path is truncated.

Includes "..." at the end of the path if the path is too long. Path truncates at 4096 characters.

**error:** string (`FTP_RESPONSE` only)  
The detailed error message recorded by the ExtraHop system.

**isReqAborted:** Boolean  
Returns true if the connection is closed before the FTP request was complete.

**isRspAborted:** Boolean (`FTP_RESPONSE` only)  
Returns true if the connection is closed before the FTP response was complete.

**method:** String  
The FTP method.

**path:** String (`FTP_RESPONSE` only)  
The path for FTP commands. Includes "..." at the beginning of the path in the event of a resync or the path is truncated. Includes "..." at the end of the path if the path is too long. Path truncates at 4096 characters.

**record:** Object (`FTP_RESPONSE` only) (version 5.0.0)  
Returns an object with all properties appropriately initialized.



The following table shows the properties available.

FTP_RESPONSE
args
cwd
error
isReqAborted
isRspAborted
method
path
reqBytes
reqL2Bytes
reqPkts
reqRTO
roundTripTime
rspBytes
rspL2Bytes
rspPkts
rspRTO
statusCode
tprocess
user

**reqBytes:** Number (FTP\_RESPONSE only)  
The number of L4 request bytes.

**reqL2Bytes:** Number (FTP\_RESPONSE only)  
The number of L2 request bytes.

**reqPkts:** Number (FTP\_RESPONSE only)  
The number of request packets.

**reqRTO:** Number (FTP\_RESPONSE only)  
The number of request RTOs.

**roundTripTime:** Number (FTP\_RESPONSE only)  
The median round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**rspBytes:** Number (FTP\_RESPONSE only)  
The number of L4 response bytes.

**rspL2Bytes:** Number (FTP\_RESPONSE only)  
The number of L2 response bytes.

**rspPkts:** Number (FTP\_RESPONSE only)  
The number of response packets.

**rspRTO:** Number (FTP\_RESPONSE only)  
The number of response RTOs.

**statusCode:** Number (FTP\_RESPONSE only)  
The FTP status code of the response.

#### FTP Status Codes

Code	Meaning
110	Restart marker replay.
120	Service ready in nnn minutes.
125	Data connection already open; transfer starting.
150	File status okay; about to open data connection.
202	Command not implemented, superfluous at this site.
211	System status, or system help reply.
212	Directory status.
213	File status.
214	Help message.
215	NAME system type.
220	Service ready for new user.
221	Service closing control connection.
225	Data connection open; no transfer in progress.
226	Closing data connection. Requested file action successful.
227	Entering Passive Mode.
228	Entering Long Passive Mode.
229	Entering Extended Passive Mode.
230	User logged in, proceed. Logged out if appropriate.
231	User logged out; service terminated.
232	Logout command noted, will complete when transfer done
250	Requested file action okay, completed.
257	"PATHNAME" created.
331	User name okay, need password.
332	Need account for login.
350	Requested file action pending further information.
421	Service not available, closing control connection.
425	Can't open data connection.
426	Connection closed; transfer aborted.
430	Invalid username or password.

Code	Meaning
434	Requested host unavailable.
450	Requested file action not taken.
451	Requested action aborted. Local error in processing.
452	Requested action not taken.
501	Syntax error in parameters or arguments.
502	Command not implemented.
503	Bad sequence of commands.
504	Command not implemented for that parameter.
530	Not logged in.
532	Need account for storing files.
550	Requested action not taken. File unavailable.
551	Requested action aborted. Page type unknown.
552	Requested file action aborted. Exceeded storage allocation.
553	Requested action not taken. File name not allowed.
631	Integrity protected reply.
632	Confidentiality and integrity protected reply.
633	Confidentiality protected reply.
10054	Connection reset by peer.
10060	Cannot connect to remote server.
10061	Cannot connect to remote server. The connection is active refused.
10066	Directory not empty.
10068	Too many users, server is full.

**tprocess:** Number (FTP\_RESPONSE only)

The server processing time, expressed in milliseconds (equivalent to `rspTimeToFirstPayload - reqTimeToLastByte`). Will return NaN on malformed and aborted responses, or if the timing is not valid.

**user:** String

The user name, if available. In some cases, such as when login events are encrypted, the user name is not available.

## HL7

(version 4.0.18766+)

The HL7 class allows retrieval of metrics available during the `HL7_REQUEST` and `HL7_RESPONSE` events.

*Go to [Classes and Events](#).*

### Events

#### HL7\_REQUEST

Fires on every HL7 request processed by the device.

*Go to [Classes and Events](#).*

#### HL7\_RESPONSE

Fires on every HL7 response processed by the device.

*Go to [Classes and Events](#).*

### Method

**commitRecord():** void (`HL7_RESPONSE` only) (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**ackCode:** String (`HL7_RESPONSE` only)

The two character acknowledgment code.

**ackId:** String (`HL7_RESPONSE` only)

The identifier for the message being acknowledged.

**msgId:** String

The unique identifier for this message.

**msgType:** String

The entire message type field, including the `msgId` subfield.

**record:** Object (`HL7_RESPONSE` only) (version 5.0.0)

Returns an object with all properties appropriately initialized.

The following table shows the properties available.

HL7_RESPONSE
ackCode
ackId
msgId
msgType
roundTripTime
tprocess
version

**roundTripTime:** Number (`HL7_RESPONSE` only)

The median round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**segments:** Array

An array of objects where each object is of type `(name: XYZ, fields: array of strings)`.

**subfieldDelimiter:** String

Supports non-standard field delimiters.

**tprocess:** Number (HL7\_RESPONSE only)

The server processing time, expressed in milliseconds. Will return NaN on malformed and aborted responses, or if the timing is not valid.

**version:** String

The version advertised in the MSH segment.

**Note:** The amount of buffered data is limited by the following capture option:  
`("message_length_max": number)`

## HTTP

The HTTP class allows retrieval of metrics available during the `HTTP_REQUEST` and `HTTP_RESPONSE` events.

[Go to \*Classes and Events\*.](#)

### Events

#### HTTP\_REQUEST

Fires on every HTTP request processed by the device.

[Go to \*Classes and Events\*.](#)

#### HTTP\_RESPONSE

Fires on every HTTP response processed by the device.

[Go to \*Classes and Events\*.](#)

### Methods

**commitRecord():** void (`HTTP_RESPONSE` only) (version 5.0.0)  
Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

**findHeaders(name:String):** Array

Allows access to HTTP header values. The result is an array of header objects (with **name** and **value** properties) where the names match the prefix of the string passed to `findHeaders`. Refer to **Example: HTTP Header Object** for more information.

**parseQuery(String):** Object (version 3.10.17757+)

Function that accepts a query string and returns an object with names and values corresponding to those in the query string. Example:

```
var query = HTTP.parseQuery(HTTP.query);
debug("user id: " + query.userid);
```

### Properties

**age:** Number

For `HTTP_REQUEST` events, the time from the first byte of the request until the last seen byte of the request. For `HTTP_RESPONSE` events, the time from the first byte of the request until the last seen byte of the response. The time is expressed in milliseconds. Returns a valid value on malformed and aborted requests. Returns NaN on expired requests and responses, or if the timing is invalid.

**contentType:** String

The value in the HTTP content-type header.

**cookies:** Array (version 3.10.17757+)

An array of objects representing cookies, containing properties corresponding to the content of each cookie. For example:

```
var cookies = HTTP.cookies,
    cookie,
```

```
i;  
for (i = 0; i < cookies.length; i++) {  
  cookie = cookies[i];  
  if (cookie.domain) {  
    debug("domain: " + cookie.domain);  
  }  
}
```

**headers:** Object

An array-like object that allows access to HTTP header names and values. Access a specific header using one of these methods:

**string property:**

The name of the header, accessible in a dictionary-like fashion. For example:

```
var headers = HTTP.headers;  
session = headers["X-Session-Id"];  
accept = headers.accept;
```

**numeric property:**

Corresponds to the order in which the headers appear on the wire. The returned object has a name and a value property. Numeric properties are useful for iterating over all the headers and disambiguating headers with duplicate names. For example:

```
for (i = 0; i < headers.length; i++) {  
  hdr = headers[i];  
  debug("headers[" + i + "].name: " + hdr.name);  
  debug("headers[" + i + "].value: " + hdr.value);  
}
```

**Note:** Saving HTTP.headers to the Flow store does not save all of the individual header values. It is a best practice to save the individual header values to the Flow store. Refer to Appendix-A for details.

**headersRaw:** String (version 5.0.0)

The unmodified block of HTTP headers, expressed as a string.

**host:** String

The value in the HTTP host header.

**isDesync:** Boolean

Returns true if the protocol parser became desynchronized due to missing packets.

**isPipelined:** Boolean

Returns true if the request is pipelined.

**isReqAborted:** Boolean

Returns true if the connection is closed before the HTTP request was complete.

**isRspAborted:** Boolean (HTTP\_RESPONSE only)

Returns true if the connection is closed before the HTTP response was complete.

**isRspChunked:** Boolean (HTTP\_RESPONSE only)  
Returns true if the response is chunked.

**isRspCompressed:** Boolean  
Returns true if the response is compressed.

**method:** String  
The HTTP method such as POST and GET.

**origin:** IPAddress | String  
The value in X-Forwarded-For or true-client-ip header.

**path:** String  
The path portion of the URI: /path/.

**payload: Buffer** (version 4.0.21449+)  
The  $n$  first bytes of HTTP request or response payload (data past the headers), where  $n$  is the number specified in the trigger. When configuring the trigger in the Web UI, select the HTTP\_RESPONSE or HTTP\_REQUEST event, click **Show advanced options**, and enter the number of payload bytes to buffer. If the payload was compressed, the decompressed content is returned.

Example of how to use HTTP payload analysis:

```

/* Extract the user name based on a pattern "user=*" from payload of a
login URI that
has "auth/login" as a URI substring. */

if (HTTP.payload && /auth\/login/i.test(HTTP.uri)) {
  var user = /user=(.*)\&/i.exec(HTTP.payload);
  if (user != null) {
    Flow.store.user = user[1];
  }
}

```

**Note:** If two HTTP payload buffering triggers are assigned to the same device, the higher value is used and the value of HTTP.payload will be the same for both triggers.

**query:** String (HTTP\_REQUEST only)  
The query string portion of the URI: query=string. This typically follows the URL and is separated from it by a question mark. Multiple query strings are separated by an ampersand (&) or semi-colon (;) delimiter.

**record:** Object (HTTP\_RESPONSE only) (version 5.0.0)  
Returns an object with all properties appropriately initialized.

The following table shows the properties available.

HTTP_RESPONSE
contentType
host
isPipelined



HTTP_RESPONSE
isReqAborted
isRspAborted
isRspChunked
isRspCompressed
method
origin
query
referer
reqBytes
reqL2Bytes
reqPkts
reqRTO
reqSize
reqTimeToLastByte
roundTripTime
rspBytes
rspL2Bytes
rspPkts
rspRTO
rspSize
rspTimeToFirstHeader
rspTimeToFirstPayload
rspTimeToLastByte
rspVersion
statusCode
thinkTime
title
tprocess
uri
userAgent

**referer:** String  
The value in the HTTP referrer header.

**reqBytes:** Number (HTTP\_RESPONSE only)  
The number of L4 request bytes.

**reqL2Bytes:** Number (HTTP\_RESPONSE only)

The number of request L2 bytes.

**reqPkts:** Number (HTTP\_RESPONSE only)  
The number of request packets.

**reqRTO:** Number (HTTP\_RESPONSE only)  
The number of request RTOs.

**reqSize:** Number  
The size of the request payload, expressed in bytes. Does not count the HTTP header and only counts the number of bytes in the body of the request.

**reqTimeToLastByte:** Number  
Time from the first byte of the request until the last byte of the request, expressed in milliseconds. Will return NaN on expired requests and responses, or if the timing is not valid.

**roundTripTime:** Number (HTTP\_RESPONSE only)  
The median TCP round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**rspBytes:** Number (HTTP\_RESPONSE only)  
The number of L4 response bytes.

**rspL2Bytes:** Number (HTTP\_RESPONSE only)  
The number of response L2 bytes.

**rspPkts:** Number (HTTP\_RESPONSE only)  
The number of response packets.

**rspRTO:** Number (HTTP\_RESPONSE only)  
The number of response RTOs.

**rspSize:** Number (HTTP\_RESPONSE only)  
The size of the response payload, expressed in bytes. Does not count the HTTP header and only counts the number of bytes in the body of the response.

**rspTimeToFirstHeader:** Number (HTTP\_RESPONSE only)  
The time from the first byte of the request until the status line that precedes the response headers, expressed in milliseconds. Will return NaN on malformed and aborted responses, or if the timing is not valid.

**rspTimeToFirstPayload:** Number (HTTP\_RESPONSE only)  
The time from the first byte of the request until the first payload byte of the response, expressed in milliseconds. Returns zero value when the response does not contain payload. Will return NaN on malformed and aborted responses, or if the timing is not valid.

**rspTimeToLastByte:** Number (HTTP\_RESPONSE only)  
The time from the first byte of the request until the last byte of the response, expressed in milliseconds. Will return NaN on malformed and aborted responses, or if the timing is not valid.

**rspVersion:** String (HTTP\_RESPONSE only)  
The HTTP version.

**statusCode:** Number (HTTP\_RESPONSE only)  
The HTTP status code of the response.

**Note:** A status code of 0 is returned when there is not a valid HTTP\_RESPONSE returned.

**title:** String (HTTP\_RESPONSE only)  
The value in the title element of the HTML content, if present.

**thinkTime:** Number (version 4.1.22976+)

The time elapsed between the server having transferred the response to the client and the client transferring a new request to the server, expressed in milliseconds. Will return NaN if there is no valid measurement.

**tprocess:** Number (HTTP\_RESPONSE only)

The server processing time, expressed in milliseconds (equivalent to `rspTimeToFirstPayload - reqTimeToLastByte`). Will return NaN on malformed and aborted responses, or if the timing is not valid.

**uri:** String

The URI without a query string: `f.q.d.n/path/`.

**userAgent:** String (HTTP\_REQUEST only)

The value in the HTTP user-agent header.

### Deprecated

**payloadText:** String

Deprecated. Use `payload` instead.

### See Also

- **Example: Customer ID Header**
- **Example: SOAP Request**
- **Example: HTTP Header Object**
- **Example: Session Table**
- **Example: Trigger-Based Application Definition**

## IBMMQ

The IBMMQ class allows retrieval of metrics available during the `IBMMQ_REQUEST` and `IBMMQ_RESPONSE` events.

[Go to \*Classes and Events\*.](#)

**Note:** The IBMMQ protocol supports EBCDIC encoding.

### Events

#### IBMMQ\_REQUEST

Fires on every IBMMQ request processed by the device.

[Go to \*Classes and Events\*.](#)

#### IBMMQ\_RESPONSE

Fires on every IBMMQ response processed by the device.

[Go to \*Classes and Events\*.](#)

### Methods

**commitRecord():** void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

Different properties are returned for the record of `IBMMQ_REQUEST` and `IBMMQ_RESPONSE`. See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**channel:** String

The communication channel name.

**correlationId:** String (version 3.8.15928+)

The IBMMQ correlation ID.

**error:** String

The error string corresponding to the error code on the wire.

**messageId:** String (version 3.8.15928+)

The IBMMQ message ID.

**method:** String

The wire protocol request/response method name.

**Note:** Wireshark users may notice some method names used by ExtraHop differ from those used by Wireshark. These are:

ExtraHop	Wireshark
ASYNC_MSG_V7	ASYNC_MESSAGE
MQCLOSEv7	SOCKET_ACTION
MQGETv7	REQUEST_MSGS

MQGETv7_REPLY	NOTIFICATION
---------------	--------------

**msgFormat:** String

The message format.

**msgSize:** Number

The size of the IBMMQ message, expressed in bytes.

**payload:** **Buffer** (version 4.0.21257+)

For `MQPUT`, `MQPUT1`, `MQGET_REPLY`, `ASYNC_MSG_V7`, and `MESSAGE_DATA` messages, the payload is set to an instance of the **Buffer** class and could be converted to string using `toString()` or formatted using `unpack` commands. Large queue messages (those greater than approximately 32K) may be broken into more than one segment and, in those cases, a trigger will fire for each segment but only the first segment will have a non-null payload.

For all other messages, it is null.

**pcfError:** String

The error string corresponding to the error code on the wire for the PCF channel.

**pcfMethod:** String

The wire protocol request/response method name for the PCF channel.

**pcfWarning:** String

The warning string corresponding to the warning string on the wire for the PCF channel.

**queue:** String

The local queue name or null if there was no `MQOPEN`, `MQOPEN_REPLY`, `MQSP1 (Open)`, or `MQSP1_REPLY` seen.

**queueMgr:** String

The local queue manager or null if there was no `INITIAL_DATA` seen at the start of the connection.

**record:** Object (version 5.0.0)

Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

IBMMQ_REQUEST	IBMMQ_RESPONSE
channel	channel
correlationId	correlationId
messageId	error
method	messageId
msgFormat	method
msgSize	msgFormat
queue	msgSize
queueMgr	queue
reqBytes	queueMgr

IBMMQ_REQUEST	IBMMQ_RESPONSE
reqL2Bytes	resolvedQueue
reqPkts	resolvedQueueMgr
reqRTO	roundTripTime
resolvedQueue	rspBytes
resolvedQueueMgr	rspL2Bytes
	rspPkts
	rspRTO
	warning

**reqBytes:** Number  
The number of application-level request bytes.

**reqL2Bytes:** Number  
The number of request L2 bytes.

**reqPkts:** Number  
The number of request packets.

**reqRTO:** Number  
The number of request RTOs.

**resolvedQueue:** String  
The resolved queue name from `MQGET_REPLY`, `MQPUT_REPLY`, or `MQPUT1_REPLY`. For a remote queue, this will be different from `IBMMQ.queue`.

**resolvedQueueMgr:** String  
The resolved queue manager from `MQGET_REPLY`, `MQPUT_REPLY`, or `MQPUT1_REPLY`. For a remote queue, this will be different from `IBMMQ.queueMgr`.

**rfh:** Array of Strings (version 4.1.4.24670)  
The strings found in the optional RFH header. If there is no RFH header or no strings, the array will be empty.

**roundTripTime:** Number  
The median round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**rspBytes:** Number  
The number of application-level response bytes.

**rspL2Bytes:** Number  
The number of response L2 bytes.

**rspPkts:** Number  
The number of request packets.

**rspRTO:** Number  
The number of response RTOs.

**warning:** String  
The warning string corresponding to the warning string on the wire.

### Deprecated

**objectHandle:** String (version 5.0.0)

Deprecated. Do not use this property.

## ICA

The ICA class allows retrieval of metrics available during the `ICA_OPEN`, `ICA_AUTH`, `ICA_TICK`, and `ICA_CLOSE` events.

[Go to \*\*Classes and Events\*\*.](#)

### Events

#### ICA\_AUTH

Fires when the ICA authentication is complete.

[Go to \*\*Classes and Events\*\*.](#)

#### ICA\_CLOSE

Fires when the ICA session is torn down.

[Go to \*\*Classes and Events\*\*.](#)

#### ICA\_OPEN

Fires right after the ICA application first loads.

[Go to \*\*Classes and Events\*\*.](#)

#### ICA\_TICK

Fires periodically while the user interacts with the ICA application.

Once `ICA_LOAD` has fired at least once, the `ICA_TICK` event will be fired when either **networkLatency** or **clientLatency** is reported.

**networkLatency** is reported when a specific ICA packet from the client contains latency information. The latency in that packet is reported as **networkLatency**.

**clientLatency** is reported when a packet from the client on the EUEM channel reports the result of a single ICA round-trip measurement. The value of that measurement is reported as **clientLatency**.

**Note:** **clientLatency** is only available via the API. It is not supported in the UI.

[Go to \*\*Classes and Events\*\*.](#)

### Methods

**commitRecord():** void (`ICA_CLOSE`, `ICA_OPEN`, and `ICA_TICK` only) (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

Different properties are returned for the record of `ICA_OPEN`, `ICA_TICK`, and `ICA_CLOSE`. A record is not available for `ICA_AUTH`. See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**application:** String

The name of the application that is being launched.

**authDomain:** String (version 3.10.20084+)

The Windows authentication domain to which the user belongs.

**channels:** Array (`ICA_TICK` only)



An array of objects containing information about virtual channels seen since the last tick event. Each object has the following properties:

- name:** String  
The name of the virtual channel.
- description:** String  
The friendly description of the channel name.
- clientBytes:** Integer  
The number of bytes sent by the client for that channel.
- serverBytes:** Integer  
The number of bytes sent by the server for the channel.
- client:** String  
The name of the client machine. This is a name that is advertised by the ICA client and is usually the hostname of the client machine.
- clientBytes:** Number (ICA\_TICK and ICA\_CLOSE only)  
The number of application level client bytes.
- clientCGPMsgCount:** Number (ICA\_TICK only)  
The number of client CGP messages since the last tick event.
- clientLatency:** Number (ICA\_TICK only)  
The current client-advertised latency in milliseconds.
- clientL2Bytes:** Number (ICA\_TICK and ICA\_CLOSE only)  
The number of L2 client bytes.
- clientMsgCount:** Number (ICA\_TICK only)  
The number of client messages since the last tick event.
- clientPkts:** Number (ICA\_TICK and ICA\_CLOSE only)  
The number of client packets.
- clientRTO:** Number (ICA\_TICK and ICA\_CLOSE only)  
The number of client RTOs.
- clientType:** String  
The user-agent equivalent to ICA. This is the type of the ICA client.
- frameCutDuration:** Number (ICA\_TICK only)  
Frame cut duration, as reported by EUEM beacon.
- frameSendDuration:** Number (ICA\_TICK only)  
The frame send duration, as reported by EUEM beacon.
- host:** String (version 3.10.20084+)  
The host name of the Citrix server.
- isAborted:** Boolean (ICA\_CLOSE only)  
Returns true if the application failed to launch successfully.
- isCleanShutdown:** Boolean (ICA\_CLOSE only)  
Returns true if the application shut down cleanly.
- isEncrypted:** Boolean  
Returns true if the application is encrypted using RC5 encryption.
- isSharedSession:** Boolean  
Returns true if the application is launched over an existing connection.

**launchParams:** String (version 3.9.16980+)  
Returns a string that represents the parameters.

**loadTime:** Number  
The load time of the given application, expressed in milliseconds.

**Note:** The load time is recorded only for the initial application load. The ExtraHop system does not measure load time for applications launched over existing sessions and instead reports the initial load time on subsequent application loads. Use `ICA.isSharedSession` to distinguish between initial and subsequent application loads.

**loginTime:** Number (`ICA_OPEN`, `ICA_TICK`, and `ICA_CLOSE` only)  
The user login time, expressed in milliseconds.

**Note:** The login time is recorded only for the initial application load. The ExtraHop system does not measure login time for applications launched over existing sessions and instead reports the initial login time on subsequent application loads. Use `ICA.isSharedSession` to distinguish between initial and subsequent application loads.

**networkLatency:** Number (`ICA_TICK` only)  
The network latency as reported by EUEM beacon.

**Note:** The UI may see some network latency even if the EUEM beacon is disabled.

**record:** Object (`ICA_CLOSE`, `ICA_OPEN`, and `ICA_TICK` only) (version 5.0.0)  
Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

<code>ICA_CLOSE</code>	<code>ICA_OPEN</code>	<code>ICA_TICK</code>
application	application	application
authDomain	authDomain	authDomain
client	client	client
clientBytes	clientType	clientBytes
clientL2Bytes	host	clientCGPMsgCount
clientPkts	isEncrypted	clientL2Bytes
clientRTO	isSharedSession	clientLatency
clientType	launchParams	clientMsgCount
host	loadTime	clientPkts
isAborted	loginTime	clientRTO
isCleanShutdown	user	clientType
isEncrypted		frameCutDuration

ICA_CLOSE	ICA_OPEN	ICA_TICK
isSharedSession		frameSendDuration
launchParams		host
loadTime		isEncrypted
loginTime		isSharedSession
roundTripTime		launchParams
serverBytes		loadTime
serverL2Bytes		loginTime
serverPkts		networkLatency
serverRTO		roundTripTime
user		serverBytes
		serverCGPMsgCount
		serverL2Bytes
		serverMsgCount
		serverPkts
		serverRTO
		user

**roundTripTime:** Number (ICA\_TICK and ICA\_CLOSE only)

The median round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**serverBytes:** Number (ICA\_TICK and ICA\_CLOSE only)

The number of application-level server bytes.

**serverCGPMsgCount:** Number (ICA\_TICK only)

The number of CGP server messages since the last tick event.

**serverL2Bytes:** Number (ICA\_TICK and ICA\_CLOSE only)

The number of L2 server bytes.

**serverMsgCount:** Number (ICA\_TICK only)

The number of server messages since the last tick event.

**serverPkts:** Number (ICA\_TICK and ICA\_CLOSE only)

The number of server packets.

**serverRTO:** Number (ICA\_TICK and ICA\_CLOSE only)

The number of server RTOs.

**user:** String

The name of the user, if available.

### Deprecated

**authTicket:** String (version 3.7.14867+)

Use **user** instead.

## ICMP

The ICMP class allows retrieval of metrics available during the `ICMP_MESSAGE` event.

[Go to \*Classes and Events\*.](#)

### Events

#### ICMP\_MESSAGE

Fires on every ICMP message processed by the device.

[Go to \*Classes and Events\*.](#)

### Methods

**commitRecord():** void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

#### gwAddr: IPAddress

For a Redirect message, the address of the gateway to which traffic for the network specified in the internet destination network field of the original datagram's data should be sent. Returns null for all other messages.

Message	ICMPv4 Type	ICMPv6 Type
Redirect Message	5	n/a

#### hopLimit: Number

The ICMP packet time to live or hop count.

#### isError: Boolean

Returns true for messages types in the following table.

Message	ICMPv4 Type	ICMPv6 Type
Destination Unreachable	3	1
Redirect	5	n/a
Source Quench	4	n/a
Time Exceeded	11	3
Parameter Problem	12	4
Packet Too Big	n/a	2

#### isQuery: Boolean

Returns true for messages types in the following table.

Message	ICMPv4 Type	ICMPv6 Type
Echo Request	8	128
Information Request	15	n/a

Message	ICMPv4 Type	ICMPv6 Type
Timestamp request	13	n/a
Address Mask Request	17	n/a
Router Discovery	10	151
Multicast Listener Query	n/a	130
Router Solicitation (NDP)	n/a	133
Neighbor Solicitation	n/a	135
ICMP Node Information Query	n/a	139
Inverse Neighbor Discovery Solicitation	n/a	141
Home Agent Address Discovery Solicitation	n/a	144
Mobile Prefix Solicitation	n/a	146
Certification Path Solicitation	n/a	148

**isReply:** Boolean

Returns true for message types in the following table.

Message	ICMPv4 Type	ICMPv6 Type
Echo Reply	0	129
Information Reply	16	n/a
Timestamp Reply	14	n/a
Address Mask Reply	18	n/a
Multicast Listener Done	n/a	132
Multicast Listener Report	n/a	131
Router Advertisement (NDP)	n/a	134
Neighbor Advertisement	n/a	136
ICMP Node Information Response	n/a	140
Inverse Neighbor Discovery Advertisement	n/a	142
Home Agent Address Discovery Reply Message	n/a	145
Mobile Prefix Advertisement	n/a	147
Certification Path Advertisement	n/a	149

**msg: Buffer**

A Buffer containing up to `message_length_max` bytes of the ICMP message. The `message_length_max` option is configured in the ICMP profile in the running config.

The following running config example changes the ICMP `message_length_max` from its default of 4096 bytes to 1234 bytes:

```
"capture": {
  "app_proto": {
```

```

    "ICMP": {
      "message_length_max": 1234
    }
  }
}

```

**msgCode:** Number  
The ICMP message code.

**msgID:** Number  
The ICMP message identifier for Echo Request, Echo Reply, Timestamp Request, Timestamp Reply, Information Request, and Information Reply messages. Returns null for all other message types.

ICMP Message ID

Message	ICMPv4 Type	ICMPv6 Type
Echo Request	8	128
Echo Reply	0	129
Timestamp Request	13	n/a
Timestamp Reply	14	n/a
Information Request	15	n/a
Information Reply	16	n/a

**msgLength:** Number  
The length of the ICMP message, expressed in bytes.

**msgText:** String  
The descriptive text for the message (e.g., `echo request` or `port unreachable`).

**msgType:** Number  
The ICMP message type.

ICMPv4

Type	Message
0	Echo Reply
1 and 2	<i>Reserved</i>
3	Destination Unreachable
4	Source Quench
5	Redirect Message
6	Alternate Host Address (deprecated)
7	<i>Reserved</i>
8	Echo Request
9	Router Advertisement
10	Router Solicitation
11	Time Exceeded

Type	Message
12	Parameter Problem: Bad IP header
13	Timestamp
14	Timestamp Reply
15	Information Request (deprecated)
16	Information Reply (deprecated)
17	Address Mask Request (deprecated)
18	Address Mask Reply (deprecated)
19	<i>Reserved</i>
20-29	<i>Reserved</i>
30	Traceroute (deprecated)
31	Datagram Conversion Error (deprecated)
32	Mobile Host Redirect (deprecated)
33	Where Are You (deprecated)
34	Here I Am (deprecated)
35	Mobile Registration Request (deprecated)
36	Mobile Registration Reply (deprecated)
37	Domain Name Request (deprecated)
38	Domain Name Reply (deprecated)
39	Simple Key-Management for Internet Protocol (deprecated)
40	Photuris (deprecated)
41	ICMP experimental
42-255	<i>Reserved</i>

#### ICMPv6

Type	Message
1	Destination Unreachable
2	Packet Too Big
3	Time Exceeded
4	Parameter Problem
100	Private Experimentation
101	Private Experimentation
127	Reserved for expansion of ICMPv6 error messages
128	Echo Request
129	Echo Reply
130	Multicast Listener Query

Type	Message
131	Multicast Listener Report
132	Multicast Listener Done
133	Router Solicitation
134	Router Advertisement
135	Neighbor Solicitation
136	Neighbor Advertisement
137	Redirect Message
138	Router Renumbering
139	ICMP Node Information Query
140	ICMP Node Information Response
141	Inverse Neighbor Discovery Solicitation Message
142	Inverse Neighbor Discovery Advertisement Message
143	Multicast Listener Discovery (MLDv2) reports
144	Home Agent Address Discovery Request Message
145	Home Agent Address Discovery Reply Message
146	Mobile Prefix Solicitation
147	Mobile Prefix Advertisement
148	Certification Path Solicitation
149	Certification Path Advertisement
151	Multicast Router Advertisement
152	Multicast Router Solicitation
153	Multicast Router Termination
155	RPL Control Message
200	Private Experimentation
201	Private Experimentation
255	Reserved for expansion of ICMPv6 informational messages

**nextHopMTU:** Number

For an ICMPv4 Destination Unreachable or an ICMPv6 Packet Too Big message, the maximum transmission unit of the next-hop link. Returns null for all other messages.

Message	ICMPv4 Type	ICMPv6 Type
Destination Unreachable	3	n/a
Packet Too Big	n/a	2

**pointer:** Number

For a Parameter Problem message, the octet of the original datagram's header where the error was detected. Returns null for all other messages.



Message	ICMPv4 Type	ICMPv6 Type
Parameter Problem	12	4

**record:** Object (version 5.0.0)

Returns an object with all properties appropriately initialized.

The following table shows the properties available.

ICMP_MESSAGE
gwAddr
hopLimit
msgCode
msgId
msgLength
msgText
msgType
nextHopMTU
pointer
seqNum
version

**seqNum:** Number

The ICMP sequence number for Echo Request, Echo Reply, Timestamp Request, Timestamp Reply, Information Request, and Information Reply messages. Null is returned for all other messages.

**version:** Number

The ICMP version. Can be either 4 or 6.

## IPAddress

The IPAddress class allows setting and retrieval of IP address attributes. IPAddress is the type of IP address properties available on the Flow class.

*Go to [Classes and Events](#).*

### Methods

**IPAddress**(ip:String | Number, [mask:Number])

Constructor for the IPAddress class that takes two parameters:

**ip**: String

The IP address string in CIDR format.

**mask**: Number

The subnet mask in a numerical format, representing the number of leftmost '1' bits in the mask (optional).

### Instance Methods

**mask**(mask:Number): IPAddress

Sets the subnet mask of the IPAddress object. Takes one parameter:

**mask**: Number

The subnet mask in a numerical format, representing the number of leftmost '1' bits in the mask (optional).

**toString**(): String

Converts the IPAddress object to a printable string.

### Properties

**hostNames**: Array of Strings

An array of hostnames associated with the IPAddress.

**isBroadcast**: Boolean

Returns true if the IP address is a broadcast address.

**isLinkLocal**: Boolean

Returns true if the IP address is a link local address (169.254.0.0/16).

**isMulticast**: Boolean

Returns true if the IP address is a multicast address.

**isRFC1918**: Boolean

Returns true if the IP address belongs to one of the RFC1918 private IP ranges (10.0.0.0/8, 172.16.0.0, 192.168.0.0/16). Always returns false for IPv6 addresses.

**isV4**: Boolean

Returns true if the IP address is an IPv4 address.

**isV6**: Boolean

Returns true if the IP address is an IPv6 address.

## Kerberos

(version 5.0.0)

The Kerberos class allows the retrieval of metrics available during the `KERBEROS_REQUEST` and `KERBEROS_RESPONSE` events.

[Go to \*Classes and Events\*.](#)

## Events

### **KERBEROS\_REQUEST**

Fires on every Kerberos AS-REQ and TGS-REQ processed by the device.

[Go to \*Classes and Events\*.](#)

### **KERBEROS\_RESPONSE**

Fires on every Kerberos AS-REP and TGS-REP processed by the device.

[Go to \*Classes and Events\*.](#)

## Methods

**commitRecord():** void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

Different properties are returned for the record of `KERBEROS_REQUEST` and `KERBEROS_RESPONSE`. See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

## Properties

**addresses:** Array of Objects (`KERBEROS_REQUEST` only)

The addresses from which the requested ticket is valid.

**cNames:** Array of Strings

The name portions of the principal identifier.

**cNameType:** String

The type for the cNames field.

**cRealm:** String

The client's realm.

**error:** String (`KERBEROS_RESPONSE` only)

The error returned.

**eType:** Array of Numbers (`KERBEROS_REQUEST` only)

An array of the preferred encryption methods.

**from:** String (`KERBEROS_REQUEST` only)

in the `AS_REQ` and `TGS_REQ` message types, the time when the requested ticket is to be postdated to.

**kdcOptions:** Object (`KERBEROS_REQUEST` only)

An object containing booleans for each option flag in `AS_REQ` and `TGS_REQ` messages.

**msgType:** String

The message type. Possible values are:

- AP\_REP
- AP\_REQ
- AS\_REP
- AS\_REQ

- AUTHENTICATOR
- ENC\_AS\_REP\_PART
- ENC\_KRB\_CRED\_PART
- ENC\_KRB\_PRIV\_PART
- ENC\_P\_REP\_PART
- ENC\_TGS\_REP\_PART
- ENC\_TICKET\_PART
- KRB\_CRED
- KRB\_ERROR
- KRB\_PRIV
- KRB\_SAFE
- TGS\_REP
- TGS\_REQ
- TICKET

**paData:** Array of Objects  
The pre-authentication data.

**processingTime:** Number (`KERBEROS_RESPONSE` only)  
The processing time, expressed in milliseconds.

**realm:** String  
The server's realm. In an `AS_REQ` message type, this is the client's realm.

**record:** Object (version 5.0.0)  
Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

KERBEROS_REQUEST	KERBEROS_RESPONSE
cNames	cNames
cNameType	cNameType
cRealm	cRealm
eType	error
from	msgType
msgType	processingTime
realm	realm
reqBytes	roundTripTime
reqL2Bytes	rspBytes
reqPkts	rspL2Bytes
reqRTO	rspPkts
sNames	rspRTO
sNameType	sNames
till	sNameType

**sNames:** Array of Strings  
The name portions of the server principal identifier.

**sNameType:** String

The type for the sNames field.

**ticket:** Object (KERBEROS\_REQUEST only)

A newly issued ticket in RESPONSE or a ticket to authenticate the client to the server in an AP\_REQ message.

**till:** String (KERBEROS\_REQUEST only)

The expiration date requested by the client in a ticket request.

## LDAP

The LDAP class allows retrieval of metrics available during the `LDAP_REQUEST` and `LDAP_RESPONSE` events.

[Go to \*Classes and Events\*.](#)

### Events

#### LDAP\_REQUEST

Fires on every LDAP request processed by the device.

[Go to \*Classes and Events\*.](#)

#### LDAP\_RESPONSE

Fires on every LDAP response processed by the device.

[Go to \*Classes and Events\*.](#)

### Methods

**commitRecord():** void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

Different properties are returned for the record of `LDAP_REQUEST` and `LDAP_RESPONSE`. See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**bindDN:** String (`LDAP_REQUEST` only, version 3.8.16379+)

The bind DN of the LDAP request.

**dn:** String

The LDAP distinguished name (DN). If no DN is set, `<ROOT>` will be returned instead.

**error:** String (`LDAP_RESPONSE` only)

The LDAP short error string as defined in the protocol (e.g., `noSuchObject`).

Result Code	Result String
1	operationsError
2	protocolError
3	timeLimitExceeded
4	sizeLimitExceeded
7	authMethodNotSupported
8	strongerAuthRequired
11	adminLimitExceeded
12	unavailableCriticalExtension
13	confidentialityRequired
16	noSuchAttribute
17	undefinedAttributeType
18	inappropriateMatching

Result Code	Result String
19	constraintViolation
20	attributeOrValueExists
21	invalidAttributeSyntax
32	NoSuchObject
33	aliasProblem
34	invalidDNSSyntax
36	aliasDeferencingProblem
48	inappropriateAuthentication
49	invalidCredentials
50	insufficientAccessRights
51	busy
52	unavailable
53	unwillingToPerform
54	loopDetect
64	namingViolation
65	objectClassViolation
66	notAllowedOnNonLeaf
67	notAllowedOnRDN
68	entryAlreadyExists
69	objectClassModsProhibited
71	affectsMultipleDSAs
80	other

**errorDetail:** String (LDAP\_RESPONSE only)

The LDAP error detail, when available for that error type (e.g., `protocolError : historical protocol version requested`, use LDAPv3 instead).

**method:** String

The LDAP method.

**msgSize:** Number

The size of the LDAP message, expressed in bytes.

**record:** Object (version 5.0.0)

Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

LDAP_REQUEST	LDAP_RESPONSE
bindDN	dn

LDAP_REQUEST	LDAP_RESPONSE
dn	error
method	errorDetail
msgSize	method
reqBytes	msgSize
reqL2Bytes	roundTripTime
reqPkts	rspBytes
reqRTO	rspL2Bytes
saslMechanism	rspPkts
searchFilter	rspRTO
searchScope	saslMechanism
	tprocess

**reqBytes:** Number (version 3.9.17182+)  
The number of request bytes.

**reqL2Bytes:** Number (version 3.9.17182+)  
The number of request L2 bytes.

**reqPkts:** Number (version 3.9.17182+)  
The number of request packets.

**reqRTO:** Number (version 3.9.17182+)  
The number of request RTOs.

**roundTripTime:** Number (version 3.9.17182+)  
The median round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**rspBytes:** Number (version 3.9.17182+)  
The number of response bytes.

**rspL2Bytes:** Number (version 3.9.17182+)  
The number of response L2 bytes.

**rspPkts:** Number (version 3.9.17182+)  
The number of response packets.

**rspRTO:** Number (version 3.9.17182+)  
The number of response RTOs.

**saslMechanism:** String (version 3.10.19298+)  
The string that defines the SASL mechanism to identify and authenticate a user to a server.

**searchAttributes:** Array (LDAP\_REQUEST only, version 4.0.19468+)  
The attributes to return from objects that match the filter criteria.

**searchFilter:** String (LDAP\_REQUEST only, version 4.0.19468+)  
The mechanism to allow certain entries in the subtree and exclude others.

**searchScope:** String (LDAP\_REQUEST only, version 4.0.19468+)  
The depth of a search within the search base.

**tprocess:** Number (LDAP\_RESPONSE only)



The server processing time, expressed in milliseconds. Will return NaN on malformed and aborted responses, or if the timing is not valid or is not available. Available for the following:

- BindRequest
- SearchRequest
- ModifyRequest
- AddRequest
- DelRequest
- ModifyDNRequest
- CompareRequest
- ExtendedRequest

## LLDP

(version 4.0.19680+)

The LLDP class allows retrieval of metrics available during the `LLDP_FRAME` events.

*Go to **Classes and Events**.*

### Events

#### **LLDP\_FRAME**

Fires on every LLDP frame processed by the device.

*Go to **Classes and Events**.*

### Properties

#### **chassisId: Buffer**

The chassis ID, obtained from the chassisId data field, or type-length-value (TLV).

#### **chassisIdSubtype: Number**

The chassis ID subtype, obtained from the chassisID TLV.

#### **destination: String**

The destination MAC address.

#### **optTLVs: Array**

An array containing the optional TLVs. Each TLV is an object with the following properties:

##### **customSubtype: Number**

The subtype of an organizationally specific TLV.

##### **isCustom: Boolean**

Returns true if the object is an organizationally specific TLV.

##### **oui: Integer**

The organizationally unique identifier for organizationally specific TLVs.

##### **type: Number**

The type of TLV

##### **value: String**

The value of the TLV.

#### **portId: Buffer**

The port ID, obtained from the portId TLV.

#### **portIdSubtype: Number**

The port ID subtype, obtained from the portId TLV.

#### **source: Device**

The device sending the LLDP frame.

#### **ttl: Number**

The time to live, expressed in seconds. This is the length of time during which the information in this frame is valid, starting with when the information is received.

## Memcache

The Memcache class allows retrieval of metrics available during the `MEMCACHE_REQUEST` and `MEMCACHE_RESPONSE` events.

*Go to [Classes and Events](#).*

### Events

#### **MEMCACHE\_REQUEST**

Fires on every memcache request processed by the device.

*Go to [Classes and Events](#).*

#### **MEMCACHE\_RESPONSE**

Fires on every memcache response processed by the device.

*Go to [Classes and Events](#).*

### Methods

**commitRecord():** void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

The different properties are returned for the record of `MEMCACHE_REQUEST` and `MEMCACHE_RESPONSE`. See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**accessTime:** Number (`MEMCACHE_RESPONSE` only)

The access time, expressed in milliseconds. Available only if the first key that was requested produced a hit.

**error:** String (`MEMCACHE_RESPONSE` only)

The detailed error message recorded by the ExtraHop system.

**hits:** Array (`MEMCACHE_RESPONSE` only)

An array of objects with the following properties:

**key:** String | Null

The Memcache key for which this was a hit, if available.

**size:** Number

The size of the value returned for the key, expressed in bytes.

**isBinaryProtocol:** Boolean

Returns true if the request/response corresponds to the binary version of the memcache protocol.

**isNoReply:** Boolean (`MEMCACHE_REQUEST` only)

Returns true if the request has the "noreply" keyword and therefore should never receive a response (text protocol only).

**isRspImplicit:** Boolean (`MEMCACHE_RESPONSE` only)

Returns true if the response was implied by a subsequent response from the server (binary protocol only).

**method:** String

The Memcache method (as recorded in ExtraHop metrics).

**misses:** Array (`MEMCACHE_RESPONSE` only)

An array of objects with the following property:

**key:** String | Null

The Memcache key for which this was a miss, if available.

**record:** Object (version 5.0.0)

Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

MEMCACHE_REQUEST	MEMCACHE_RESPONSE
isBinaryProtocol	accessTime
isNoReply	error
method	hits
reqBytes	isBinaryProtocol
reqL2Bytes	isRspImplicit
reqPkts	method
reqRTO	misses
reqSize	roundTripTime
vbucket	rspBytes
	rspL2Bytes
	rspPkts
	rspRTO
	statusCode
	vbucket

**reqBytes:** Number

The number of application-level request bytes.

**reqKeys:** Array

An array containing the Memcache key strings sent with the request.

**reqL2Bytes:** Number

The number of request L2 bytes.

**reqPkts:** Number

The number of request packets.

**reqRTO:** Number (MEMCACHE\_REQUEST only)

The number of request RTOs.

**reqSize:** Number

The size of the value in the request (if any), expressed in bytes. Note that methods such as `set` include values, while `get` and `delete` do not.

**roundTripTime:** Number

The median round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**rspBytes:** Number

The number of application-level response bytes.

**rspL2Bytes:** Number  
The number of response L2 bytes.

**rspPkts:** Number  
The number of response packets.

**rspRTO:** Number (MEMCACHE\_RESPONSE only)  
The number of response RTOs.

**statusCode:** String (MEMCACHE\_RESPONSE only)  
The Memcache status code. For the binary protocol, ExtraHop metrics prepend the method to status codes other than NO\_ERROR, but the statusCode property does not. Refer to the examples for code that matches the behavior of ExtraHop metrics.

**vbucket:** Number  
The Memcache vbucket, if available (binary protocol only).

### See Also

- **Example: Memcache Hits and Misses**
- **Example: Memcache Key Parsing**

## MetricCycle

The MetricCycle class represents an interval where stats were published. It is valid on the following events:

- METRIC\_CYCLE\_BEGIN
- METRIC\_CYCLE\_END
- METRIC\_RECORD\_COMMIT

[Go to \*Classes and Events\*.](#)

### Events

#### METRIC\_CYCLE\_BEGIN

Fires when a metric interval begins.

[Go to \*Classes and Events\*.](#)

#### METRIC\_CYCLE\_END

Fires when a metric interval ends.

[Go to \*Classes and Events\*.](#)

### Properties

#### id: String

A string representing the metric cycle. Possible values are:

- 30sec
- 5min
- 1hr
- 24hr

#### interval: Object

An object containing **from** and **until** properties, expressed in milliseconds since the epoch.

#### store: Object

An object that retains information across all the METRIC\_RECORD\_COMMIT events that occur during a metric cycle, that is, from the METRIC\_CYCLE\_BEGIN event to the METRIC\_CYCLE\_END event. This object is analogous to Flow.store in capture. MetricCycle.store is shared among triggers for METRIC\_\* events. It is cleared at the end of a metric cycle.

### See Also

- **Example: Use the Metric Cycle Store**

## MetricRecord

The MetricRecord class allows access to the current set of metrics in `METRIC_RECORD_COMMIT`.

*Go to **Classes and Events**.*

### Events

#### **METRIC\_RECORD\_COMMIT**

Fires when a metric record is committed to the datastore. Provides access to the object, metric type, cycle, metric fields (for example, for `extrahop.device.http_server`, properties include `req`, `rsp`, `rsp_error`, `status_code`, etc.).

*Go to **Classes and Events**.*

### Properties

**fields:** Object

An object containing metric values. The properties are the field names and the values can be numbers, **Topset**, **Dataset** or **Sampleset**.

**id:** String

The metric type. For example, `extrahop.device.http_server`.

**object:** Object

The object the metric applies to. For device, application, or VLAN metrics, this property will contain a Device, Application, or VLAN instance, respectively. For capture metrics (e.g., `extrahop.-capture.net`), the property will contain the global Network class.

**time:** Number

The time that the metric record will be published with.

### See Also

- **Example: Create a Custom Trouble Group**
- **Example: Topset Key Matching**
- **Example: Use the Metric Cycle Store**

## MongoDB

(version 4.0.13997+)

The MongoDB class allows retrieval of metrics available during the `MONGODB_REQUEST` and `MONGODB_RESPONSE` events.

*Go to [Classes and Events](#).*

### Events

#### **MONGODB\_REQUEST**

Fires on every MongoDB request processed by the device.

*Go to [Classes and Events](#).*

#### **MONGODB\_RESPONSE**

Fires on every MongoDB response processed by the device.

*Go to [Classes and Events](#).*

### Methods

**commitRecord():** void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

The different properties are returned for the record of `MONGODB_REQUEST` and `MONGODB_RESPONSE`. See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**collection:** String

The name of the database collection specified in the current request.

**database:** String

The MongoDB database instance. In some cases, such as when login events are encrypted, the database name is not available.

**error:** String (`MONGODB_RESPONSE` only)

The detailed error message recorded by the ExtraHop system.

**isReqAborted:** Boolean

Returns true if the connection is closed before the MongoDB request was complete.

**isReqTruncated:** Boolean

Returns true if the request document(s) size is greater than the maximum payload document size.

**isRspAborted:** Boolean (`MONGODB_RESPONSE` only)

Returns true if the connection is closed before the MongoDB response was complete.

**method:** String

The MongoDB database method (appears under **Methods** in the user interface).

**opcode:** String

The MongoDB operational code on the wire protocol, which may differ from the MongoDB method used.

**record:** Object (version 5.0.0)

Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.



The following table shows the properties available for the record of each event.

MONGODB_REQUEST	MONGODB_RESPONSE
collection	collection
database	database
isReqAborted	error
isReqTruncated	isRspAborted
method	method
opcode	opcode
reqBytes	roundTripTime
reqL2Bytes	rspBytes
reqPkts	rspL2Bytes
reqRTO	rspPkts
reqSize	rspRTO
reqTimeToLastByte	rspSize
user	rspTimeToFirstByte
	rspTimeToLastByte
	tprocess
	user

**reqBytes:** Number  
The number of application-level request bytes.

**reqL2Bytes:** Number  
The number of request L2 bytes.

**reqPkts:** Number  
The number of request packets.

**reqRTO:** Number  
The number of request RTOs.

**reqSize:** Number  
The size of the request record at L7, expressed in bytes.

**reqTimeToLastByte:** Number  
The time from the first byte of the request until the last byte of the request, expressed in milliseconds.

**request:** Array  
An array of JS objects parsed from MongoDB request payload documents. Total document size is limited to 4K.

If BSON documents are truncated, **isReqTruncated** flag is set. Truncated values are represented as follows:

- Primitive string values like code, code with scope, and binary data are partially extracted.
- Objects and Arrays are partially extracted.
- All other primitive values like Numbers, Dates, RegExp, etc., are substituted with null.

If no documents are included in the request, an empty array is returned.

**roundTripTime:** Number

The median round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**rspBytes:** Number

The number of application-level response bytes.

**rspL2Bytes:** Number

The number of response L2 bytes.

**rspPkts:** Number

The number of response packets.

**rspRTO:** Number

The number of response RTOs.

**rspSize:** Number (MONGODB\_RESPONSE only)

The size of the response record at L7, expressed in bytes.

**rspTimeToFirstByte:** Number (MONGODB\_RESPONSE only)

The time from the first byte of the request until the first byte of the response, expressed in milliseconds. Will return NaN on malformed and aborted responses, or if the timing is not valid.

**rspTimeToLastByte:** Number (MONGODB\_RESPONSE only)

The time from the first byte of the request until the last byte of the response, expressed in milliseconds. Will return NaN on malformed and aborted responses, or if the timing is not valid.

**tprocess:** Number (MONGODB\_RESPONSE only)

The time to process the request, expressed in milliseconds (equivalent to `rspTimeToFirstByte - reqTimeToLastByte`). Will return NaN on malformed and aborted responses, or if the timing is not valid.

**user:** String

The user name, if available. In some cases, such as when login events are encrypted, the user name is not available.

## MSMQ

(version 5.0.0)

The MSMQ class allows for retrieval of metrics available during the `MSMQ_MESSAGE` event.

*Go to [Classes and Events](#).*

### Events:

#### MSMQ\_MESSAGE

Fires on every MSMQ user message processed by the device.

*Go to [Classes and Events](#).*

### Methods

**commitRecord():** void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

## Properties:

**adminQueue:** String

The name of the administration queue of the message.

**correlationId:** Buffer

The application-generated correlation ID of the message.

**dstQueueMgr:** String

The destination message broker of the message.

**isEncrypted:** Boolean

Returns true if the payload is encrypted.

**label:** String

The label or description of the message.

**msgClass:** String

The message class of the message. Possible values are:

- MQMSG\_CLASS\_NORMAL
- MQMSG\_CLASS\_ACK\_REACH\_QUEUE
- MQMSG\_CLASS\_NACK\_ACCESS\_DENIED
- MQMSG\_CLASS\_NACK\_BAD\_DST\_Q
- MQMSG\_CLASS\_NACK\_BAD\_ENCRYPTION
- MQMSG\_CLASS\_NACK\_BAD\_SIGNATURE
- MQMSG\_CLASS\_NACK\_COULD\_NOT\_ENCRYPT
- MQMSG\_CLASS\_NACK\_HOP\_COUNT\_EXCEEDED
- MQMSG\_CLASS\_NACK\_NOT\_TRANSACTIONAL\_MSG
- MQMSG\_CLASS\_NACK\_NOT\_TRANSACTIONAL\_Q
- MQMSG\_CLASS\_NACK\_PURGED
- MQMSG\_CLASS\_NACK\_Q\_EXCEEDED\_QUOTA
- MQMSG\_CLASS\_NACK\_REACH\_QUEUE\_TIMEOUT
- MQMSG\_CLASS\_NACK\_SOURCE\_COMPUTER\_GUID\_CHANGED
- MQMSG\_CLASS\_NACK\_UNSUPPORTED\_CRYPTO\_PROVIDER
- MQMSG\_CLASS\_ACK\_RECEIVE
- MQMSG\_CLASS\_NACK\_Q\_DELETED
- MQMSG\_CLASS\_NACK\_Q\_PURGED
- MQMSG\_CLASS\_NACK\_RECEIVE\_TIMEOUT
- MQMSG\_CLASS\_NACK\_RECEIVE\_TIMEOUT\_AT\_SENDER
- MQMSG\_CLASS\_REPORT

**msgId:** Number

The MSMQ message id of the message.

**payload:** Buffer

The body of the MSMQ message.

**priority:** Number

The priority of the message. This can be a number between 0 and 7.

**queue:** String

The name of the destination queue of the message.

**receiverBytes:** Number

The number of L4 receiver bytes.

**receiverL2Bytes:** Number

The number of L2 receiver bytes.

**receiverPkts:** Number  
The number of receiver packets

**receiverRTO:** Number  
The number of receiver RTOs.

**record:** Object (version 5.0.0)  
Returns an object with all properties appropriately initialized.

The following table shows the properties available.

MSMQ_MESSAGE
adminQueue
dstQueueMgr
isEncrypted
label
msgClass
msgId
priority
queue
receiverBytes
>receiverL2Bytes
receiverPkts
receiverRTO
responseQueue
roundTripTime
senderBytes
senderL2Bytes
senderPkts
senderRTO
srcQueueMgr

**responseQueue:** String  
The name of the response queue of the message.

**roundTripTime:** Number  
The median round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**senderBytes:** Number  
The number of sender L4 bytes.

**senderL2Bytes:** Number  
The number of sender L2 Bytes.

**senderPkts:** Number  
The number of sender packets.

**senderRTO:** Number  
The number of sender RTOs.

**srcQueueMgr:** String  
The source message broker of the message.

## Network

The network class allows adding custom metrics at the global level.

Go to [Classes and Events](#).

Use the following functions to record custom metrics associated with networks. Refer to the ExtraHop Data-types section for an overview of the data types.

- **metricAddCount**(*metric\_name*:String, *count*:Number, [*highPrecision*: bool]): void
- **metricAddDataset**(*metric\_name*:String, *val*:Number, [*freq*:Number], [*highPrecision*: bool]): void
- **metricAddDetailCount**(*metric\_name*:String, *key*:String | IPAddress, *count*:Number, [*highPrecision*: bool]): void
- **metricAddDetailSnap**(*metric\_name*:String, *key*:String | IPAddress, *count*:Number, [*highPrecision*: bool]): void
- **metricAddDetailDataset**(*metric\_name*:String, *key*:String | IPAddress, *val*:Number, [*freq*:Number], [*highPrecision*: bool]): void
- **metricAddDetailMax**(*metric\_name*:String, *key*:String | IPAddress, *val*:Number, [*highPrecision*: bool]) void
- **metricAddDetailSampleset**(*metric\_name*:String, *key*:String | IPAddress, *val*:Number, [*highPrecision*: bool]): void
- **metricAddMax**(*metric\_name*:String, *val*:Number, [*highPrecision*: bool]): void
- **metricAddSampleset**(*metric\_name*:String, *val*:Number, [*highPrecision*: bool]): void
- **metricAddSnap**(*metric\_name*:String, *count*:Number, [*highPrecision*: bool]): void

The optional `highPrecision` flag will enable one second granularity for the metrics when set to true.

### Notes:

- Freq is the number of occurrences of the value being passed in. If the value is not passed in, the value of freq is 1. The freq argument is useful in cases when you want to simultaneously record multiply occurrences of particular values in a dataset.
- When NaN is passed to a `metricAdd*` function, it is silently discarded.
- All count parameters for `metricAdd*` functions only accept a non-zero, positive integer between 1 and  $2^{64}$ .

### See Also

- **Example: Database Trigger**
- **Example: Parse Syslog Over TCP with Universal Payload Analysis**
- **Example: Session Table**
- **Example: SOAP Request**

## NFS

The NFS class allows retrieval of metrics available during the `NFS_REQUEST` and `NFS_RESPONSE` events.

[Go to \*Classes and Events\*.](#)

### Events

#### **NFS\_REQUEST**

Fires on every NFS request processed by the device.

[Go to \*Classes and Events\*.](#)

#### **NFS\_RESPONSE**

Fires on every NFS response processed by the device.

[Go to \*Classes and Events\*.](#)

### Methods

**commitRecord():** void (`NFS_RESPONSE` only) (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**accessTime:** Number (`NFS_RESPONSE` only)

The time it took for the server to access a file on disk, expressed in milliseconds. For NFS, it is the time from every non-pipelined READ and WRITE command in an NFS flow until the payload containing the response is recorded by the ExtraHop system. Will return NaN on malformed and aborted responses, or if the timing is not valid or is not applicable.

**authMethod:** String (version 4.0.21474+)

The method for authenticating users.

**error:** String (`NFS_RESPONSE` only)

The detailed error message recorded by the ExtraHop system.

**fileHandle: Buffer**

The file handle returned by the server on LOOKUP, CREATE, SYMLINK, MKNOD, LINK, or REaddirPLUS operations.

**isCommandFileInfo:** Boolean (version 4.0.21474+)

Returns true if the command is a file info.

**isCommandRead:** Boolean

Returns true if the command is a read.

**isCommandWrite:** Boolean

Returns true if the command is a write.

**method:** String

The NFS method (appears under **Methods** in the UI).

**offset:** Number (`NFS_REQUEST` only, version 4.0.21300+)

The file offset associated with READ and WRITE NFS commands.

**record:** Object (`NFS_RESPONSE` only) (version 5.0.0)

Returns an object with all properties appropriately initialized.

The following table shows the properties available.

NFS_RESPONSE
accessTime
authMethod
error
isCommandFileInfo
isCommandRead
isCommandWrite
method
offset
renameDirChanged
reqBytes
reqL2Bytes
reqPkts
reqRTO
reqSize
resource
roundTripTime
rspBytes
rspL2Bytes
rspPkts
rspRTO
rspSize
statusCode
user
version

**renameDirChanged:** Boolean (NFS\_REQUEST only)  
Returns true if a resource rename request includes a directory move.

**reqBytes:** Number (NFS\_RESPONSE only)  
The number of L4 request bytes.

**reqL2Bytes:** Number (NFS\_RESPONSE only)  
The number of L2 request bytes.

**reqPkts:** Number (NFS\_RESPONSE only)  
The number of request packets.

**reqRTO:** Number (NFS\_REQUEST only)  
The number of request RTOs.

**reqSize:** Number



The size of the request record at L7, expressed in bytes.

**resource:** String

The path and filename, concatenated together.

**roundTripTime:** Number (NFS\_RESPONSE only)

The median round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**rspBytes:** Number (NFS\_RESPONSE only)

The number of L4 response bytes.

**rspL2Bytes:** Number (NFS\_RESPONSE only)

The number of L2 response bytes.

**rspPkts:** Number (NFS\_RESPONSE only)

The number of response packets.

**rspRTO:** Number (NFS\_RESPONSE only)

Number of response RTOs.

**rspSize:** Number (NFS\_RESPONSE only)

The size of the response record at L7, expressed in bytes.

**statusCode:** String (version 4.0.21474+)

The NFS status code of the request or response.

**user:** String

The Linux user ID on the system. Uses the format `uid:xxxx@ip_address`.

**version:** Number

The NFS version.

## Record

(version 5.0.0)

Go to [Classes and Events](#).

A record is a JSON object used to send information to the ExtraHop Explore appliance.

Built-in protocols provide access to a default record on events that represent the completion of transactions (for example, `HTTP.record` on `HTTP_RESPONSE`) or on partial transaction updates. (`Flow.record` on `FLOW_RECORD`). Not all events will result in a record.

You can create a custom record

### Properties

**type:** String

The ID of the type of record type to be created, which cannot begin with a tilde (~).

**fields:** Object

One or more key-value pairs.

### Examples

For built-in protocols, there is an accessor to retrieve a prepopulated record. This will return an object with all the fields initialized appropriately for the protocol and trigger event.

```
record = HTTP.record;
```

A record is a javascript object.

```
record = {  
  field1: 'myfield1',  
  field2: 'myfield2'  
};
```

To commit a custom record, use `commitRecord`.

```
commitRecord('custom_record', record);
```

A built-in record can be the basis for a custom record.

```
record = HTTP.record;  
record.session = HTTP.headers["X-Session-Id"]  
commitRecord('custom_record', record);
```

You can also export a record using one of the Remote classes like `Remote.MongoDB`.

```
Remote.MongoDB.insert('collection', record); // record.toJSON()
```

## Remote.HTTP

(version 4.1.23251+)

The Remote.HTTP class allows submission of HTTP requests to an HTTP Open Data Stream Configuration previously configured in the ExtraHop Admin UI. This includes the ability to use HTTP REST APIs. Consult with your ExtraHop appliance administrator for the possible values to use for HTTP Data Stream Configuration names.

**Note:** To use `Remote.HTTP`, you must have previously configured an HTTP data stream in the **Open Data Streams** pane of the ExtraHop Admin UI.

Go to [Classes and Events](#).

### Methods

#### request

Submits an HTTP REST request to an HTTP Data Stream Configuration previously configured in the ExtraHop Admin UI.

#### Syntax:

```
Remote.HTTP("name").request("method", {path: "path", [headers: headers],  
[payload: "payload"]})
```

```
Remote.HTTP.request("method", {path: "path", [headers: headers],  
[payload: "payload"]})
```

#### Parameters:

**method:** String

String specifying the HTTP method to be used.

- GET
- HEAD
- POST
- PUT
- DELETE
- TRACE
- OPTIONS
- CONNECT
- PATCH

**options:** Object

The options object has the following properties:

**path:** String

The string specifying the request path.

**headers:** Object

The optional object specifying the request headers.

It is possible to compress the outgoing HTTP requests by using the Content-Encoding header.

```
'Content-Encoding': 'gzip'
```

The following values are supported for this compression header:

- gzip
- deflate

**payload:** String | **Buffer**

The optional string or **Buffer** specifying the request payload.

**name:** String

The name of the HTTP Data Stream Configuration previously configured in the ExtraHop Admin UI. If no name is specified, the request will go to the first (default) Data Stream Configuration.

**Return Value:**

Returns **true** if the request is queued, otherwise returns **false**.

## Helper Methods

The following helper methods allow you to more easily make use of the most common HTTP methods.

- **Remote.HTTP.delete**
- **Remote.HTTP.get**
- **Remote.HTTP.patch**
- **Remote.HTTP.post**
- **Remote.HTTP.put**

**Syntax:**

```
Remote.HTTP("name").delete({path: "path", [headers: headers],  
[payload: "payload"]})
```

```
Remote.HTTP.delete({path: "path", [headers: headers], [payload: "payload"]})
```

```
Remote.HTTP("name").get({path: "path", [headers: headers],  
[payload: "payload"]})
```

```
Remote.HTTP.get({path: "path", [headers: headers], [payload: "payload"]})
```

```
Remote.HTTP("name").patch({path: "path", [headers: headers],  
[payload: "payload"]})
```

```
Remote.HTTP.patch({path: "path", [headers: headers], [payload: "payload"]})
```

```
Remote.HTTP("name").post({path: "path", [headers: headers],  
[payload: "payload"]})
```

```
Remote.HTTP.post({path: "path", [headers: headers], [payload: "payload"]})
```

```
Remote.HTTP("name").put({path: "path", [headers: headers],  
[payload: "payload"]})
```

```
Remote.HTTP.put({path: "path", [headers: headers], [payload: "payload"]})
```

### Parameters:

All of these helper methods take the following parameters:

**options:** Object

The options object has the following properties:

**path:** String

The string specifying the request path.

**headers:** Object

The optional object specifying the request headers.

**payload:** String

The optional string specifying the request payload.

**name:** String

The name of the HTTP Data Stream Configuration previously configured in the ExtraHop Admin UI. If no name is specified, the request will go to the first (default) Data Stream Configuration.

### Return Value:

Returns **true** if the request is queued, otherwise returns **false**.

### Examples:

#### HTTP GET

The following example will issue an HTTP GET request to the HTTP configuration `my_destination` and a path that is the URI, including query string variables, that you want the request to be sent to.

```
Remote.HTTP("my_destination").get( { path: "?example=example1&example2=my_  
data" } );
```

#### HTTP POST

The following example will issue an HTTP POST request to the HTTP configuration `my_destination`, the path that is the URI you want the request to be sent to and a payload. The payload can be data similar to what an HTTP client would send, a JSON blob, XML, or whatever else you want to send.

```
Remote.HTTP("my_destination").post( { path: "/", payload: "dataI want to send" } );
```

### Custom HTTP Headers

The following example defines a Javascript object with keys to represent the header names and their corresponding values and provide that in a call as the value for the `headers` key.

```
var my_json = { example: "my_data", example1: 42, example2: false };
var headers = { "Content-Type": "application/json" };
Remote.HTTP("my_destination").post( { path: "/", headers: headers, payload:
JSON.stringify(my_json) } );
```

### See Also:

- **Example: Send Data to Elasticsearch with Remote.HTTP**
- **Example: Send Information to Azure Table Service with Remote.HTTP**

## Remote.Kafka

(version 5.0.0)

The `Remote.Kafka` class allows the submission of messages to a Kafka server.

**Note:** To use `Remote.Kafka`, you must have previously configured a Kafka data stream in the **Open Data Streams** pane of the ExtraHop Admin UI.

Go to [Classes and Events](#).

### Methods

#### send

Sends an array of messages to a single topic with an option to indicate which Kafka partition the messages will be sent to.

#### Syntax:

```
Remote.Kafka.send({"topic": "topic", "messages": [messages],
["partition": partition]})
```

```
Remote.Kafka("name").send({"topic": "topic", "messages": [messages],
["partition": partition]})
```

#### Parameters:

If `Remote.Kafka.send` is called with one argument, that argument must be a JavaScript object that contains the following fields:

**topic:** String

A string corresponding to the topic associated with the Kafka send.

**messages:** Array

An array of messages to be sent. An element in this array cannot be an array itself.

**partition:** Number

An optional non-negative integer corresponding to the Kafka partition the messages will be sent to. The send will fail silently if the number provided exceeds the number of partitions on the Kafka cluster associated with the given target. This value is ignored unless **Manual Partitioning** is selected as the partitioning strategy for the target in the **Open Data Stream** configuration in the ExtraHop Admin UI.

**Return Value:**

None

**Examples:**

```
Remote.Kafka.send({"topic": "my_topic", "messages": ["hello world", 42, DHCP.msgType], "partition": 2});
```

```
Remote.Kafka("my-target").send({"topic": "my_topic", "messages": [HTTP.query, HTTP.uri]});
```

**send**

Sends messages to a single topic.

**Syntax:**

```
Remote.Kafka.send("topic", message1, message2, etc...)
```

```
Remote.Kafka("my-target").send("topic", message1, message2, etc...)
```

**Parameters:**

If `Remote.Kafka.send` is called with multiple arguments, the following fields are required:

**topic:** String

A string corresponding to the topic associated with the Kafka send.

**messages:** String | Number

The messages to be sent. This cannot be an array.

**Return Value:**

None.

**Examples:**

```
Remote.Kafka.send("my_topic", HTTP.query, HTTP.uri);
```

```
Remote.Kafka("my-target").send("my_topic", HTTP.query, HTTP.uri);
```

## Remote.MongoDB

(version 4.0.18429+)

The Remote.MongoDB class allows insertion, removal, and updating of documents in collections in MongoDB.

**Note:** To use Remote.MongoDB, you must have previously configured a MongoDB data stream in the **Open Data Streams** pane of the ExtraHop Admin UI.

Go to [Classes and Events](#).

### Methods

#### insert

Inserts a document or array of documents into a collection, and handles both add and modify operations.

#### Syntax:

```
Remote.MongoDB.insert("db.collection", document);
```

```
Remote.MongoDB("name").insert("db.collection", document);
```

#### Parameters:

**collection:** String

The name of a group of MongoDB documents.

**document:** Object

The JSON-formatted document to insert into the collection.

**name:** String (version 4.1.24352+)

The name of the host as it appears in the ExtraHop Open Data Streams UI. If no host is specified, the default host will be used.

#### Return Value:

Returns **true** if the request is queued, otherwise returns **false**.

#### Examples:

```
Remote.MongoDB.insert('sessions.sess_www',
  {
    'session_id': "100",
    'path': "/index.html",
    'host': "www.extrahop.com",
    'status': "500",
    'src_ip': "10.10.1.120",
    'dst_ip': "10.10.1.100"
  }
);
```



```
var x = Remote.MongoDB.insert('test.tbc', {'example': 1});
if (x) {
    Network.metricAddCount('perf_trigger_success', 1);
}
else {
    Network.metricAddCount('perf_trigger_error', 1);
}
```

Refer to

<http://docs.mongodb.org/manual/reference/method/db.collection.insert/#db.collection.insert> for more information.

## remove

Removes documents from a collection.

### Syntax:

```
Remote.MongoDB.remove("db.collection", document, [justOnce]);
```

```
Remote.MongoDB("name").remove("db.collection", document, [justOnce]);
```

### Parameters:

**collection:** String

The name of a group of MongoDB documents.

**document:** Object

The JSON-formatted document to remove from the collection.

**justOnce:** Boolean

An optional boolean parameter used to limit the removal to just one document. Set to "true" to limit the deletion. The default value is false.

**name:** String (version 4.1.24352+)

The name of the host as it appears in the ExtraHop Open Data Streams UI. If no host is specified, the default host will be used.

### Return Value:

Returns **true** if the request is queued, otherwise returns **false**.

### Example:

```
var x = Remote.MongoDB.remove('test.tbc', {qty: 100000}, false);
if (x) {
    Network.metricAddCount('perf_trigger_success', 1);
}
else {
    Network.metricAddCount('perf_trigger_error', 1);
}
```

Refer to

<http://docs.mongodb.org/manual/reference/method/db.collection.remove/#db.collection.remove> for more information.

## Update

Modifies an existing document or documents in a collection.

### Syntax:

```
Remote.MongoDB.update("db.collection", document, update, [{"upsert":true, "multi":true}]);
```

```
Remote.MongoDB("name").update("db.collection", document, update, [{"upsert":true, "multi":true}]);
```

### Parameters:

**collection:** String

The name of a group of MongoDB documents.

**document:** Object

The JSON-formatted document that specifies which documents to update or insert, if upsert option is set to true.

**update:** Object

The JSON-formatted document that specifies how to update the specified documents.

**name:** String (version 4.1.24352+)

The name of the host as it appears in the ExtraHop Open Data Streams UI. If no host is specified, the default host will be used.

**options:**

Optional flags that indicate the following additional update options:

**upsert:** Boolean

An optional boolean parameter to create a new document when no document matches the query data. Set to "true" to create a new document. The default value is false.

**multi:** Boolean

An optional boolean parameter to update all documents that match the query data. Set to "true" to update multiple documents. The default value is false, which updates only the first document returned.

### Return Value:

Returns **true** if the request is queued, otherwise returns **false**.

### Example:

```
var x = Remote.MongoDB.update('test.tbc', {_id: 1}, {$set: {'example':2}}, {'upsert':true, 'multi':false} );
```

```
if (x) {  
    Network.metricAddCount('perf_trigger_success', 1);  
}  
else {  
    Network.metricAddCount('perf_trigger_error', 1);  
}
```

Refer to

<http://docs.mongodb.org/manual/reference/method/db.collection.update/#db.collection.update>  
for more information.

**See Also:**

- **Example: Parse Syslog Over TCP with Universal Payload Analysis**

## Remote.Syslog

(version 4.0.18429+)

The Remote.Syslog class allows creation of remote syslog messages with specified content.

**Note:** To use `Remote.Syslog`, you must have previously configured a Syslog data stream in the **Open Data Streams** pane of the ExtraHop Admin UI.

Go to [Classes and Events](#).

Each of these methods sends a message to the configured remote syslog server with a severity corresponding to the method name using the "user" facility. You can specify the specific host using the 'name' field and using the name as it appears in the ExtraHop Open Data Streams UI. If no host is specified, the default host will be used.

- **emerg**(message: String): void
- **alert**(message: String): void
- **crit**(message: String): void
- **error**(message: String): void
- **warn**(message: String): void
- **notice**(message: String): void
- **info**(message: String): void
- **debug**(message: String): void

For instance, to send an rsyslog message to the default host for every HTTP response that includes the URI, request and response sizes, and server processing time, add the following trigger on the `HTTP_RESPONSE` event:

```
Remote.Syslog.info("eh_event=web uri=" + HTTP.uri + " req_size=" + HTTP.reqSize + "
rsp_size=" + HTTP.rspSize + " tprocess=" + HTTP.tprocess);
```

To send an rsyslog message to the host 'name' for every HTTP response that includes the URI, request and response sizes, and server processing time, add the following trigger on the `HTTP_RESPONSE` event (version 4.1.24352+):

```
Remote.Syslog("name").info("eh_event=web uri=" + HTTP.uri + " req_size=" +
HTTP.reqSize + " rsp_size=" + HTTP.rspSize + " tprocess=" + HTTP.tprocess);
```

If submitting an rsyslog message succeeds, the APIs will return true. In the case of either success or failure, the trigger will continue to execute as a failure to submit an rsyslog message is a "soft" failure. Incorrect usage of the APIs, i.e. calling them with the wrong number or type of arguments, will still result in trigger execution stopping.

### Message size

By default, the message sent to the remote server is limited to 1024 bytes, including the message header and trailer (if necessary). The message header always includes the priority and timestamp, which together are up to 30 bytes.

To increase the default message size, go to the Admin UI, click **Running Config**, and then click **Edit**. Go to the "capture" section, and under "rsyslog", add "message\_length\_max". The "message\_length\_max"

setting applies only to the message passed to the Remote.Syslog APIs, the message header does not count against the max. Sample configuration:

```
"remote": {
  "rsyslog": {
    "host": "splunkium",
    "port": 54322,
    "ipproto": "tcp",
    "message_length_max": 4000
  }
}
```

### Timestamp

The timestamp format for rsyslog messages in versions 5.0.0 defaults to UTC but can be changed to local time with an offset in the Data Stream Configuration setup.

The timestamp format for rsyslog messages is expressed in UTC in versions before 4.1.24484 and after 4.1.24504. For example:

```
2015-07-08T23:42:35.075Z
```

For versions 4.1.24484 through 4.1.24504, , the timestamp format for rsyslog messages is expressed in local time with a offset. For example:

```
2015-07-08T13:47:32.724-10:00
```

### See Also

- **Example: Device Discovery Notification**
- **Example: Parse Syslog Over TCP with Universal Payload Analysis**
- **Example: Topnset Key Matching**

## RemoteSyslog

**Note:** Deprecated. Use **Remote.Syslog** on page 132 instead.

Go to [Classes and Events](#).

Each of these methods send a message to the configured remote syslog server with a severity corresponding to the method name using the "user" facility.

- **emerg**(message: String): void
- **alert**(message: String): void
- **crit**(message: String): void
- **error**(message: String): void
- **warn**(message: String): void
- **notice**(message: String): void
- **info**(message: String): void
- **debug**(message: String): void

For instance, to send an rsyslog message for every HTTP response that includes the URI, request and response sizes, and server processing time, add the following trigger on the `HTTP_RESPONSE` event:

```
RemoteSyslog.info("eh_event=web uri=" + HTTP.uri + " req_size=" + HTTP.reqSize + "
rsp_size=" + HTTP.rspSize + " tprocess=" + HTTP.tprocess);
```

If submitting an rsyslog message succeeds, the APIs will return true. In the case of either success or failure, the trigger will continue to execute as a failure to submit an rsyslog message is a "soft" failure. Incorrect usage of the APIs, i.e. calling them with the wrong number or type of arguments, will still result in trigger execution stopping.

By default, the message sent to the remote server is limited to 1024 bytes, including the message header and trailer (if necessary). The message header always includes the priority and timestamp, which together are up to 30 bytes.

To increase the default message size, go to the **Admin UI**, click **Running Config**, and then click **Edit**. Go to the "remote" section, and under "rsyslog", add "message\_length\_max". The "message\_length\_max" setting applies only to the message passed to the RemoteSyslog APIs, the message header does not count against the max. Sample configuration:

```
"remote": {
  "rsyslog": {
    "host": "splunkium",
    "port": 54322,
    "ipproto": "tcp",
    "message_length_max": 4000
  }
}
```

## RTCP

(version 4.1.22706+)

The RTCP class allows for retrieval of metrics available during the `RTCP_MESSAGE` event.

[Go to \*Classes and Events\*.](#)

### Events

#### RTCP\_MESSAGE

Fires on every RTCP UDP packet processed by the device.

[Go to \*Classes and Events\*.](#)

### Methods

**commitRecord():** void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**callId:** String

The Call ID for associating with a SIP flow.

**packets:** Array

An array of RTCP packet objects where each object represents a packet and contains a **packetType** field. Each object has different fields based on the message type, as described below.

**packetType:** String

The type of packet. If the packet type is not recognizable, then the packetType will be "Unknown *n*" where *n* is the RTP control packet type value.

Value	Type	Name
194	SMPTE	SMPTE time-code mapping
195	IJ	Extended inter-arrival jitter report
200	SR	sender report
201	RR	receiver report
202	SDES	source description
203	BYE	goodbye
204	APP	application-defined
205	RTPFB	Generic RTP Feedback
206	PSFB	Payload-specific
207	XR	extended report
208	AVB	AVB RTCP packet
209	RSI	Receiver Summary Information
210	TOKEN	Port Mapping

Value	Type	Name
211	IDMS	IDMS Settings

**APP** packet objects have the following fields:

- name:** String  
The name chosen by the person defining the set of APP packets to be unique. Interpreted as four case-sensitive ASCII characters.
- ssrc:** Number  
The SSRC of the sender.
- value:** **Buffer**  
The optional application-dependent data.

**BYE** packet objects have the following fields:

- packetType:** Number  
Contains the number 203 to identify this as an RTCP BYE packet.

**SR** packet objects have the following fields:

- ntpTimestamp:** Number  
The NTP timestamp, converted to milliseconds since the epoch (January 1, 1970).
- reportBlocks:** Array  
An array of report objects which contain:
  - fractionLost:** Number  
The 8-bit number indicating the number of packets lost divided by the number of packets expected.
  - jitter:** Number  
An estimate of the statistical variance of the RTP data packet interarrival time, expressed in milliseconds.
  - lastSR:** Number  
The middle 32 bits of the ntp\_Timestamp received as part of the most recent RTCP sender report (SR) packet from the source SSRC. If no SR has been received yet, this field is set to zero.
  - lastSRDelay:** Number  
The delay between receiving the last SR packet from the source SSRC and sending this reception block, expressed in units of 1/65536 seconds. If no SR packet has been received yet, this field is set to zero.
  - packetsLost:** Number  
The total number of RTP data packets from the source SSRC that have been lost since the beginning of reception.
  - seqNum:** Number  
The highest sequence number received from the source SSRC.
  - ssrc:** Number  
The SSRC of the sender:
  - rtpTimestamp:** Number  
The RTP timestamp, converted to milliseconds since the epoch (January 1, 1970).
  - senderOctets:** Number



The sender octet count.

**senderPkts:** Number  
The sender packet count.

**RR** packet objects have the following fields:

**reportBlocks:** Array  
An array of report objects which contain:

**fractionLost:** Number  
The 8-bit number indicating the number of packets last divided by the number of packets expected.

**jitter:** Number  
An estimate of the statistical variance of the RTP data packet interarrival, expressed in milliseconds.

**lastSR:** Number  
The middle 32 bits of the ntp\_Timestamp received as part of the most recent RTCP sender report (SR) packet from the source SSRC. If no SR has been received yet, this field is set to zero.

**lastSRDelay:** Number  
The delay between receiving the last SR packet from the source SSRC and sending this reception report block, expressed in units of 1/65536 seconds. If no SR packet has been received yet, this field is set to zero.

**packetsLost:** Number  
The total number of RTP data packets from the source SSRC that have been lost since the beginning of reception.

**seqNum:** Number  
The highest sequence number received from the source SSRC.

**ssrc:** Number  
The SSRC of the sender.

**ssrc:** Number  
The SSRC of the sender.

**SDES** packet objects have the following fields:

**descriptionBlocks:** Array  
An array of objects that contain:

**type:** Number  
The SDES type.

SDES Type	Abbrev.	Name
0	END	end of SDES list
1	CNAME	canonical name
2	NAME	user name
3	EMAIL	user's electronic mail address
4	PHONE	user's phone number
5	LOC	geographic user location

SDES Type	Abbrev.	Name
6	TOOL	name of application or tool
7	NOTE	notice about the source
8	PRIV	private extensions
9	H323-C ADDR	H.323 callable address
10	APSI	Application Specific Identifier

**value: Buffer**

A buffer containing the text portion of the SDES packet.

**ssrc: Number**

The SSRC of the sender.

**XR** packet objects have the following fields:

**ssrc: Number**

The SSRC of the sender.

**xrBlocks: Array**

An array of report blocks which contain:

**statSummary: Object (type 6 only)**

The statSummary object contains the following properties:

**beginSeq: Number**

The beginning sequence number for the interval.

**devJitter: Number**

The standard deviation of the relative transit time between each two packet series in the sequence interval.

**devTTLorHL: Number**

The standard deviation of TTL or Hop Limit values of data packets in the sequence number range.

**dupPackets: Number**

The number of duplicate packets in the sequence number interval.

**endSeq: Number**

The ending sequence number for the interval.

**lostPackets: Number**

The number of lost packets in the sequence number interval.

**maxJitter: Number**

The maximum relative transmit time between two packets in the sequence interval, expressed in milliseconds.

**maxTTLorHL: Number**

The maximum TTL or Hop Limit value of data packets in the sequence number range.

**meanJitter: Number**

The mean relative transit time between two packet series in the sequence interval, rounded to the nearest value expressible as an RTP timestamp, expressed in milliseconds.

**meanTTLOrHL:** Number

The mean TTL or Hop Limit value of data packets in the sequence number range.

**minJitter:** Number

The minimum relative transmit time between two packets in the sequence interval, expressed in milliseconds.

**minTTLOrHL:** Number

The minimum TTL or Hop Limit value of data packets in the sequence number range.

**ssrc:** Number

The SSRC of the sender.

**type:** Number

The XR block type.

Block Type	Name
1	Loss RTE Report Block
2	Duplicate RLE Report Block
3	Packet Receipt Times Report Block
4	Receiver Reference Time Report Block
5	DLRR Report Block
6	Statistics Summary Report Block
7	VoIP Metrics Report Block
8	RTCP XP
9	Texas Instruments Extended VoIP Quality Block
10	Post-repair Loss RLE Report Block
11	Multicast Aquisition Report Block
12	IBMS Report Block
13	ECN Summary Report
14	Measurement Information Block
15	Packet Delay Variation Metrics Block
16	Delay Metrics Block
17	Burst/Gap Loss Summary Statistics Block
18	Burst/Gap Discard Summary Statistics Block
19	Frame Impairment Statistics Summary
20	Burst/Gap Loss Metrics Block
21	Burst/Gap Discard Metrics Block
22	MPEG2 Transport Stream PSI-Independent Decodability Statistics Metrics Block

Block Type	Name
23	De-Jitter Buffer Metrics Block
24	Discard Count Metrics Block
25	DRLE (Discard RLE Report)
26	BDR (Bytes Discarded Report)
27	RFISD (RTP Flows Initial Synchronization Delay)
28	RFSO (RTP Flows Synchronization Offset Metrics Block)
29	MOS Metrics Block
30	LCB (Loss Concealment Metrics Block)
31	CSB (Concealed Seconds Metrics Block)
32	MPEG2 Transport Stream PSI Decodability Statistics Block

**typeSpecific:** Number

The contents of this field depend on the block type.

**value:** Buffer

The contents of this field depend on the block type.

**voipMetrics:** Object (type 7 only)

The voipMetrics object contains the following properties:

**burstDensity:** Number

The fraction of RTP data packets within burst periods since the beginning of reception that were either lost or discarded.

**burstDuration:** Number

The mean duration, expressed in milliseconds, of the burst periods that have occurred since the beginning of reception.

**discardRate:** Number

The fraction of RTP data packets from the source that have been discarded since the beginning of reception, due to late or early arrival, under-run or overflow at the receiving jitter buffer.

**endSystemDelay:** Number

The most recently estimated end system delay, expressed in milliseconds.

**extRFactor:** Number

The external R factor quality metric. A value of 127 indicates this parameter is unavailable.

**gapDensity:** Number

The fraction of RTP data packets within inter-burst gaps since the beginning of reception that were either lost or discarded.

**gapDuration:** Number

The mean duration of the gap periods that have occurred since the beginning of reception, expressed in milliseconds.

**gmin:** Number

The gap threshold.

**jbAbsMax:** Number

The absolute maximum delay, expressed in milliseconds, that the adaptive jitter buffer can reach under worst case conditions.

**jbMaximum:** Number

The current maximum jitter buffer delay, which corresponds to the earliest arriving packet that would not be discarded, expressed in milliseconds.

**jbNominal:** Number

The current nominal jitter buffer delay, which corresponds to the nominal jitter buffer delay for packets that arrive exactly on time, expressed in milliseconds.

**lossRate:** Number

The fraction of RTP data packets from the source lost since the beginning of reception.

**mosCQ:** Number

The estimated mean opinion score for conversational quality (MOS-CQ). A value of 127 indicates this parameter is unavailable.

**mosLQ:** Number

The estimated mean opinion score for listening quality (MOS-LQ). A value of 127 indicates this parameter is unavailable.

**noiseLevel:** Number

The noise level, expressed in decibels.

**rerl:** Number

The residual echo return loss value, expressed in decibels.

**rFactor:** Number

The R factor quality metric. A value of 127 indicates this parameter is unavailable.

**roundTripDelay:** Number

The most recently calculated round-trip time (RTT) between RTP interfaces, expressed in milliseconds.

**rxConfig:** Number

The receiver configuration byte.

**signalLevel:** Number

The voice signal relative level, expressed in decibels.

**ssrc:** Number

The SSRC of the sender.

**record:** Object (version 5.0.0)

Returns an object with all properties appropriately initialized.

The following table shows the properties available.

RTCP_MESSAGE
callId
cName

## RTP

(version 4.1.22706)

The RTP class allows for retrieval of metrics available during the `RTP_OPEN`, `RTP_CLOSE` and `RTP_TICK` events.

*Go to [Classes and Events](#).*

### Events

#### **RTP\_CLOSE**

Fires when an RTP connection is closed.

*Go to [Classes and Events](#).*

#### **RTP\_OPEN**

Fires when a new RTP connection is opened.

*Go to [Classes and Events](#).*

#### **RTP\_TICK**

Fires periodically on RTP flows.

*Go to [Classes and Events](#).*

### Methods

**commitRecord():** void (`RTP_TICK` only) (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**bytes:** Number (`RTP_TICK` only)  
The number of bytes sent.

**callId:** String  
The call ID for associating with SIP flow.

**drops:** Number (`RTP_TICK` only)  
The number of dropped packets detected.

**dups:** Number (`RTP_TICK` only)  
The number of duplicate packets detected.

**jitter:** Number (`RTP_TICK` only)  
An estimate of the statistical variance of the data packet interarrival time.

**l2Bytes:** Number (`RTP_TICK` only)  
The number of L2 bytes.

**mos:** Number (`RTP_TICK` only, version 4.1.23229+)  
The estimated mean opinion score for quality.

**outOfOrder:** Number (`RTP_TICK` only)  
The number of out-of-order messages detected.

**payloadType:** String (`RTP_TICK` only)  
The type of RTP payload.

payloadTypeId	payloadType
0	ITU-T G.711 PCMU Audio
3	GSM 6.10 Audio
4	ITU-T G.723.1 Audio
5	IMA ADPCM 32kbit Audio
6	IMA ADPCM 64kbit Audio
7	LPC Audio
8	ITU-T G.711 PCMA Audio
9	ITU-T G.722 Audio
10	Linear PCM Stereo Audio
11	Linear PCM Audio
12	QCELP
13	Comfort Noise
14	MPEG Audio
15	ITU-T G.728 Audio
16	IMA ADPCM 44kbit Audio
17	IMA ADPCM 88kbit Audio
18	ITU-T G.729 Audio
25	Sun CellB Video
26	JPEG Video
28	Xerox PARC Network Video
31	ITU-T H.261 Video
32	MPEG Video
33	MPEG-2 Transport Stream
34	ITU-T H.263-1996 Video

**payloadTypeId:** Number (RTP\_TICK only)

The numeric value of the payload type. See table under **payloadType**.

**pkts:** Number (RTP\_TICK only)

The number of packets sent.

**record:** Object (RTP\_TICK only) (version 5.0.0)

Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

RTP_TICK
bytes

RTP_TICK
callId
drops
dups
jitter
l2Bytes
mos
outOfOrder
payloadType
payloadTypeId
pkts
rFactor
ssrc
version

**rFactor:** Number (RTP\_TICK only)  
The R factor quality metric.

**ssrc:** Number  
The SSRC of sender.

**version:** Number  
The RTP version number.



## Sampleset

The Sampleset class is used to represent sampleset metrics.

*Go to [Classes and Events](#).*

### Properties

**count:** Number  
The number of samples in the sampleset.

**mean:** Number  
The average value of the samples.

**sigma:** Number  
The standard deviation.

**sum:** Number  
The sum of the samples.

**sum2:** Number  
The sum of the squares of the samples.

## SDP

The SDP class allows for retrieval of Session Description Protocol (SDP) information during the `SIP_REQUEST` and `SIP_RESPONSE` events.

*Go to [Classes and Events](#).*

### Properties

**mediaDescriptions:** Array (`SIP_REQUEST` and `SIP_RESPONSE`)

An array of objects containing the following fields:

**attributes:** Array of Strings

The optional session attributes.

**bandwidth:** Array of Strings

The optional proposed bandwidth type and bandwidth to be used by the session or media.

**connectionInfo:** String

The connection data, including network type, address type and connection address. May also contain optional sub-fields, depending on the address type.

**description:** String

The session description which may contain one or more media descriptions. Each media description consists of media, port and transport protocol fields.

**encryptionKey:** String

The optional encryption method and key for the session.

**mediaTitle:** String

The title of the media stream.

**sessionDescription:** Object (`SIP_REQUEST` and `SIP_RESPONSE`)

An object containing the following fields:

**attributes:** Array of Strings

The optional session attributes.

**bandwidth:** Array of Strings

The optional proposed bandwidth type and bandwidth to be used by the session or media.

**connectionInfo:** String

The connection data, including network type, address type and connection address. May also contain optional sub-fields, depending on the address type.

**email:** String

The optional email address. If present, this can contain multiple email addresses.

**encryptionKey:** String

The optional encryption method and key for the session.

**origin:** String

The originator of the session, including username, address of the user's host, a session identifier, and a version number.

**phoneNumber:** String

The optional phone number. If present, this can contain multiple phone numbers.

**sessionInfo:** String

The session description.

**sessionName:** String  
The session name.

**timezoneAdjustments:** String  
The adjustment time and offset for a scheduled session.

**uri:** String  
The optional URI intended to provide more information about the session.

**version:** String  
The version number. This should be 0.

**timeDescriptions:** Array (`SIP_REQUEST` and `SIP_RESPONSE`)  
An array of objects containing the following fields:

**repeatTime:** String  
The session repeat time, including interval, active duration, and offsets from start time.

**time:** String  
The start time and stop times for a session.

## Session

The Session object is in-memory and global per ExtraHop appliance. It is designed to support coordination across multiple independently executing triggers. The ExtraHop Open Data Context API exposes the Session object via the management network, enabling coordination with external processes. The Session object's global state means any changes by a trigger or external process becomes visible to all other entities on the same ExtraHop appliance using the Session object. Because the Session object is in-memory, changes are not saved when you restart the ExtraHop appliance or the capture process.

Note: ECM cluster nodes do not share their global state. An ECM does not execute triggers; it only manages them.

[Go to \*Classes and Events\*.](#)

## Events

### SESSION\_EXPIRE

The `SESSION_EXPIRE` event fires periodically (in approximately 30 second increments) as long as the session table is in use. It does not fire once for every expired entry, and it does not fire immediately after an entry has expired.

[Go to \*Classes and Events\*.](#)

## Methods

**add** (key:String, value \*, [options:Object]): \*

Returns the given key in the session table. If the key is present, the corresponding value is returned without modifying the entry. If the key is not present, a new entry is created for the given key and value, and the new value is returned.

**getOptions** (key:String): Object

Returns the Options object for the entry corresponding to the one passed in through `Session.add` or `Session.replace`.

**increment** (key:String, [count:Number]): Number | Null

Atomic lookup and increment. The default count value is 1. On success, the new value is returned. If lookup fails, null is returned. If the value is not a number, an exception is thrown.

**lookup** (key:String): \*

Look up the given key in the session table and return the corresponding value. Returns null if the key is not present.

**modify** (key:String, value:\*, [options:Object]): \* (version 3.9.17050+)

Modify the entry associated with the given key. If the key is present, update the value and return the previous value. If the key is not present, no new entry is created. If options are provided, the options of the entry are updated and old options are merged with new ones. If the "expire" option is provided, the expiration timer is reset.

**remove** (key:String): \*

Removes the entry for the given key and returns the associated value.

**replace** (key:String, value:\*, [options:Object]): \* (versions 3.9.17031-3.9.17555, 3.10.18339+)

Update the entry associated with the given key. If the key is present, update the value and return the previous value. If the key is not present, add the entry and return the previous value (null). If options are provided, the options of the entry are updated and old options are merged with new ones. If the "expire" option is provided, the expiration timer is reset.

## Constants

**PRIORITY\_LOW**: Number  
Default value is 0. **Example: Session Table**

**PRIORITY\_NORMAL**: Number  
Default value is 1

**PRIORITY\_HIGH**: Number  
Default value is 2.

## Properties

**expiredKeys**: Array (`SESSION_EXPIRE` only)  
An array of objects with the following properties:

**age**: Integer  
The age of the expired object, expressed in milliseconds. Age is the amount of time elapsed between when the object in the session table was added or modified, and the `SESSION_EXPIRE` event.

**name**: String  
The key of the expired object.

**value**: Number | String | IPAddress | Boolean | Device  
The value of the entry in the session table.

Session table **options** are as follows:

**expire**: Number  
The duration after which eviction will occur, expressed in seconds. If null or undefined, the entry will be evicted only when the session table grows too large. This is the default.

**notify**: Boolean  
Indicates whether the key will be available on `SESSION_EXPIRE` events. The default value is false.

**priority**: String  
A constant, `Session.PRIORITY_{LOW, NORMAL, HIGH}`, used to determine which entries to evict if the session table grows too large. The default value is `PRIORITY_NORMAL`.

The `SESSION_EXPIRE` event is not associated with any particular flow, so triggers on `SESSION_EXPIRE` events cannot commit device metrics in the usual way (e.g., `Device.metricAdd*` or `Flow.client.device.metricAdd*`). To commit device metrics on this event, you have to add any needed Device objects to the session table using the `Device()` constructor.

## Deprecated

**update** (`key:String, value:*, [options:Object]`) \* (version 3.9.17031+)  
Deprecated. Use `Session.replace` instead.

## See Also

- **Example: Session Table**

## SIP

(version 4.1.22706+)

The SIP class allows retrieval of metrics available during the `SIP_REQUEST` and `SIP_RESPONSE` events.

[Go to \*\*Classes and Events\*\*.](#)

### Events

#### **SIP\_REQUEST**

Fires on every SIP request processed by the device.

[Go to \*\*Classes and Events\*\*.](#)

#### **SIP\_RESPONSE**

Fires on every SIP response processed by the device.

[Go to \*\*Classes and Events\*\*.](#)

### Methods

**commitRecord():** void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

The different properties are returned for the record of `SIP_REQUEST` and `SIP_RESPONSE`. See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Methods

**findHeaders**(name: String): Array

Allows access to SIP header values. The result is an array of header objects (with **name** and **value** properties) where the names match the prefix of the string passed to **findHeaders**.

### Properties

**callId:** String

The call ID for this message.

**from:** String

The contents of the From header.

**hasSDP:** Boolean

Returns true if this event includes SDP information.

**headers:** Object

An array-like object that allows access to SIP header names and values. Access a specific header using one of these methods:

**string property:**

The name of the header, accessible in a dictionary-like fashion. For example:

```
var headers = SIP.headers;
session = headers["X-Session-Id"];
accept = headers.accept;
```

**numeric property:**

The order in which headers appear on the wire. The returned object has a name and a value property. Numeric properties are useful for iterating over all the headers and disambiguating headers with duplicate names. For example:

```
for (i = 0; i < headers.length; i++) {
  hdr = headers[i];
  debug("headers[" + i + "].name: " + hdr.name);
  debug("headers[" + i + "].value: " + hdr.value);
}
```

**Note:** Saving SIP.headers to the Flow store does not save all of the individual header values. It is best practice to save the individual header values to the Flow store.

**method:** String  
The SIP method.

Method Name	Description
ACK	Confirms the client has received a final response to an INVITE request.
BYE	Terminates a call. Can be sent by either the caller or the callee.
CANCEL	Cancels any pending request
INFO	Sends mid-session information that doesn't change the session state.
INVITE	Invites a client to participate in a call session.
MESSAGE	Transports instant messages using SIP.
NOTIFY	Notify the subscriber of a new event.
OPTIONS	Queries the capabilities of servers.
PRACK	Provisional Acknowledgement.
PUBLISH	Publish an event to the server.
REFER	Ask recipient to issue a SIP request (call transfer).
REGISTER	Registers the address listed in the To header field with a SIP server.
SUBSCRIBE	Subscribes for an event of Notification from the Notifier.
UPDATE	Modifies the state of a session without changing the state of the dialog.

**processingTime:** Number (SIP\_RESPONSE only)

The time between the request and the first response, expressed in milliseconds. Will return NaN on malformed and aborted responses, or if the timing is not valid.

**record:** Object (version 5.0.0)

Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

SIP_REQUEST	SIP_RESPONSE
callId	callId
from	from
hasSDP	hasSDP
method	processingTime
reqBytes	roundTripTime
reqL2Bytes	rspBytes
reqPkts	rspL2Bytes
reqRTO	rspPkts
reqSize	rspRTO
to	rspSize
uri	statusCode
	to

**reqBytes:** Number  
The number of L4 request bytes.

**reqL2Bytes:** Number  
The number of L2 request bytes.

**reqPkts:** Number  
The number of request packets.

**reqRTO:** Number  
The number of request RTOs.

**reqSize:** Number (SIP\_REQUEST only)  
The size of the request payload, expressed in bytes. Does not include headers.

**roundTripTime:** Number  
The median round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**rspBytes:** Number  
The number of L4 response bytes.

**rspL2Bytes:** Number  
The number of L2 response bytes.

**rspPkts:** Number  
The number of response packets.

**rspRTO:** Number  
The number of response RTOs.

**rspSize:** Number (SIP\_RESPONSE only)  
The size of the response payload, expressed in bytes. Does not include headers.

**statusCode:** Number (SIP\_RESPONSE only)  
The SIP response status code.



### Provisional Responses

Number	Response
100	Trying
180	Ringing
181	Call is Being Forwarded
182	Queued
183	Session In Progress
199	Early Dialog Terminated

### Successful Responses

Number	Response
200	OK
202	Accepted
204	No Notification

### Redirection Responses

Number	Response
300	Multiple Choice
301	Moved Permanently
302	Moved Temporarily
305	Use Proxy
380	Alternative Service

### Client Failure Responses

Number	Response
400	Bad Request
401	Unauthorized
402	Payment Required
403	Forbidden
404	Not Found
405	Method Not Allowed
406	Not Acceptable
407	Proxy Authentication Required
408	Request Timeout
409	Conflict
410	Gone

Number	Response
411	Length Required
412	Conditional Request Failed
413	Request Entity Too Large
414	Request URI Too Long
415	Unsupported Media Type
416	Unsupported URI Scheme
417	Unknown Resource Priority
420	Bad Extension
421	Extension Required
422	Session Interval Too Small
423	Interval Too Brief
424	Bad Location Information
428	Use Identity Header
429	Provide Referrer Identity
430	Flow Failed
433	Anonymity Disallowed
436	Bad Identity Info
437	Unsupported Certificate
438	Invalid Identity Header
439	First Hop Lacks Outbound Support
470	Consent Needed
480	Temporarily Unavailable
481	Call/Transaction Does Not Exist
482	Loop Detected
483	Too Many Hops
484	Address Incomplete
485	Ambiguous
486	Busy Here
487	Request Terminated
488	Not Acceptable Here
489	Bad Event
491	Request Pending
493	Undecipherable
494	Security Agreement Required

### Server Failure Responses

Number	Response
500	Server Internal Error
501	Not Implemented
502	Bad Gateway
503	Service Unavailable
504	Server Timeout
505	Version Not Supported
513	Message Too Large
580	Precondition Failure

### Global Failure Responses

Name	Response
600	Busy Everywhere
603	Decline
604	Does Not Exist Anywhere
606	Not Acceptable

**to:** String  
The contents of the To header.

**uri:** String  
The URI for SIP request or response.

## SMPP

The SMPP class allows retrieval of metrics available during the `SMPP_REQUEST` and `SMPP_RESPONSE` events.

**Note:** The `mdn`, `shortcode`, and `error` properties may be null, depending on availability and relevance.

[Go to \*Classes and Events\*.](#)

### Events

#### SMPP\_REQUEST

Fires on every SMPP request processed by the device.

[Go to \*Classes and Events\*.](#)

#### SMPP\_RESPONSE

Fires on every SMPP response processed by the device.

[Go to \*Classes and Events\*.](#)

### Methods

**commitRecord():** void (`SMPP_RESPONSE` only) (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**command:** String

The SMPP command ID.

**destination:** String

The destination address as specified in the `SMPP_REQUEST`. Will be null if this is not available for the current command type.

**error:** String (`SMPP_RESPONSE` only)

The error code corresponding to `command_status`. If the command status is ROK, the value of error will be null.

**message: Buffer** (`SMPP_REQUEST` only, version 4.1.23411+)

The contents of the `short_message` field on `DELIVER_SM` and `SUBMIT_SM` messages. Will be null if unavailable or not applicable.

**record:** Object (`SMPP_RESPONSE` only) (version 5.0.0)

Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

SMPP_RESPONSE
command
destination
error

SMPP_RESPONSE
reqSize
reqTimeToLastByte
rspSize
rspTimeToFirstByte
rspTimeToLastByte
source
tprocess

**reqSize:** Number

The size of the request, expressed in bytes.

**reqTimeToLastByte:** Number

The time from the first byte of the request until the last byte of the request, expressed in milliseconds. Returns NaN on malformed and aborted requests, or if the timing is not valid.

**rspSize:** Number (SMPP\_RESPONSE only)

The size of the response, expressed in bytes.

**rspTimeToFirstByte:** Number (SMPP\_RESPONSE only)

The time from the first byte of the request until the first byte of the response, expressed in milliseconds. Will return NaN on malformed and aborted responses, or if the timing is not valid.

**rspTimeToLastByte:** Number (SMPP\_RESPONSE only)

The time from the first byte of the request until the last byte of the response, expressed in milliseconds. Will return NaN on malformed and aborted responses, or if the timing is not valid.

**source:** String

The source address as specified in the SMPP\_REQUEST. Will be null if this is not available for the current command type.

**tprocess:** Number (SMPP\_RESPONSE only)

The server processing time, expressed in milliseconds. Equivalent to `rspTimeToFirstByte - reqTimeToLastByte`. Will return NaN on malformed and aborted responses, or if the timing is not valid.

## SMTP

(version 4.0.18766+)

The SMTP class allows retrieval of metrics available during the SMTP\_REQUEST and SMTP\_RESPONSE events.

*Go to **Classes and Events**.*

### Events

#### SMTP\_REQUEST

Fires on every SMTP request processed by the device.

*Go to **Classes and Events**.*

#### SMTP\_RESPONSE

Fires on every SMTP response processed by the device.

*Go to **Classes and Events**.*

### Methods

**commitRecord():** void (SMTP\_RESPONSE only) (version 5.0.0)  
Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

### Properties

**dataSize:** Number  
The size of the attachment, expressed in bytes.

**domain:** String  
The domain of the address the message is coming from.

**error:** String (SMTP\_RESPONSE only, version 4.1.23176+)  
The error string corresponding to the status code.

**headers:** Object  
An object that allows access to SMTP header names and values.

**isEncrypted:** Boolean  
Returns true if the application is encrypted using STARTTLS encryption.

**isReqAborted:** Boolean  
Returns true if the connection is closed before the SMTP request is complete.

**isRspAborted:** Boolean (SMTP\_RESPONSE only)  
Returns true if the connection is closed before the SMTP response is complete.

**method:** String  
The SMTP method.

**record:** Object (SMTP\_RESPONSE only) (version 5.0.0)  
Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

SMTP_RESPONSE
dataSize
domain
error
isEncrypted
isReqAborted
isRspAborted
method
recipient
recipientList
reqBytes
reqL2Bytes
reqPkts
reqRTO
reqSize
reqTimeToLastByte
roundTripTime
rspBytes
rspL2Bytes
rspPkts
rspRTO
rspSize
rspTimeToFirstByte
rspTimeToLastByte
sender
statusCode
statusText
tprocess

**recipient:** String  
The address the message should be sent to.

**recipientList:** Array of Strings  
A list of recipient addresses.

**reqBytes:** Number  
The number of L4 request bytes.

**reqL2Bytes:** Number  
The number of request L2 bytes.

**reqPkts:** Number

The number of request packets.

**reqRTO:** Number

The number of request RTOs.

**reqSize:** Number

The size of the request in bytes.

**reqTimeToLastByte:** Number

The time from the first byte of the request until the last byte of the request, expressed in milliseconds. Will return NaN on malformed and aborted requests, or if the timing is not valid.

**roundTripTime:** Number

The median TCP round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**rspBytes:** Number

The number of L4 response bytes.

**rspL2Bytes:** Number

The number of response L2 bytes.

**rspPkts:** Number

The number of response packets.

**rspRTO:** Number

The number of response RTOs.

**rspSize:** Number (SMTP\_RESPONSE only)

The size of the response, expressed in bytes.

**rspTimeToFirstByte:** Number (SMTP\_RESPONSE only)

The time from the first byte of the request until the last byte of the request, expressed in milliseconds. Will return NaN on malformed and aborted requests, or if the timing is not valid.

**rspTimeToLastByte:** Number (SMTP\_RESPONSE only)

The time from the first byte of the request until the last byte of the response, expressed in milliseconds. Will return NaN on malformed and aborted requests, or if the timing is not valid.

**sender:** String

The sender of the message.

**statusCode:** Number (SMTP\_RESPONSE only)

The SMTP status code of the response.

**statusText:** String (SMTP\_RESPONSE only)

The multi-line response string.

**tprocess:** Number (SMTP\_RESPONSE only)

The server processing time, expressed in milliseconds. Equivalent to `rspTimeToFirstPayload - reqTimeToLastByte`. Will return NaN on malformed and aborted responses, or if the timing is not valid.



## SSL

The SSL class allows retrieval of metrics available during the `SSL_OPEN`, `SSL_CLOSE`, `SSL_ALERT`, `SSL_RECORD`, `SSL_HEARTBEAT`, and `SSL_RENEGOTIATE` events.

[Go to \*\*Classes and Events\*\*.](#)

### Events

#### **SSL\_ALERT**

Fires when an SSL alert record is exchanged.

[Go to \*\*Classes and Events\*\*.](#)

#### **SSL\_CLOSE**

Fires when the SSL connection is shut down.

[Go to \*\*Classes and Events\*\*.](#)

#### **SSL\_HEARTBEAT**

(version 3.10.19872+)

Fires when an SSL heartbeat record is exchanged.

[Go to \*\*Classes and Events\*\*.](#)

#### **SSL\_OPEN**

Fires when the SSL connection is first established.

[Go to \*\*Classes and Events\*\*.](#)

#### **SSL\_PAYLOAD**

(version 4.1.24320+)

Fires when the decrypted SSL payload matches the criteria configured in the associated trigger.

Depending on the **FLOW**, the payload can be found in the following:

- `Flow.client.payload`
- `Flow.payload1`
- `Flow.payload2`
- `Flow.receiver.payload`
- `Flow.sender.payload`
- `Flow.server.payload`

[Go to \*\*Classes and Events\*\*.](#)

#### **SSL\_RECORD**

(version 3.8.15910+)

Fires when an SSL record is exchanged.

[Go to \*\*Classes and Events\*\*.](#)

#### **SSL\_RENEGOTIATE**

(version 4.0.20129+)

Fires on SSL renegotiation.

[Go to \*\*Classes and Events\*\*.](#)

### Methods

**commitRecord()**: void (`SSL_ALERT`, `SSL_CLOSE`, `SSL_HEARTBEAT`, and `SSL_OPEN` only) (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

The different properties are returned for the record of `SSL_ALERT`, `SSL_CLOSE`, `SSL_HEARTBEAT`, and `SSL_OPEN`. See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

**getClientExtensionData**(extension\_name | extension\_id): **Buffer**

Returns the extension data if the extension was passed as part of the hello message from the client and had data. Returns null otherwise.

**getServerExtensionData**(extension\_name | extension\_id): **Buffer**

Returns the extension data if the extension was passed as part of the hello message from the server and had data. Returns null otherwise.

**hasClientExtension**(extension\_name | extension\_id): **boolean**

Returns true if the extension was passed as part of the hello message from the client.

**hasServerExtension**(extension\_name | extension\_id): **boolean**

Returns true if the extension was passed as part of the hello message from the server.

## Properties

**alertCode**: Number (`SSL_ALERT` only)

If the session is opaque, the value is `SSL.ALERT_LEVEL_UNKNOWN` (255). Otherwise, it corresponds to the numeric part of the `AlertDescription` data structure specified in RFC2246.

**alertLevel**: Number (`SSL_ALERT` only)

If the session is opaque, the value is `SSL.ALERT_LEVEL_UNKNOWN` (255). Otherwise, it corresponds to the numeric part of the `AlertLevel` data structure as specified in RFC2246.

**certificate**: `SSLCert`

The SSL certificate object associated with the communication. Each object has the following properties:

**fingerprint**: String

The string hex representation of the SHA-1 hash of the certificate. This is the same string shown in most browsers' certificate information dialog boxes, but without spaces. For example:

```
"55F30E6D49E19145CF680E8B7E3DC8FC7041DC81"
```

**keySize**: Number

The certificate key size.

**notAfter**: Number

The certificate expiration time in UTC.

**publicKeyExponent**: String

A string hex representation of the public key's exponent. This is the same string shown in most browsers' certificate information dialog boxes, but without spaces.

**publicKeyModulus**: String

A string hex representation of the public key's modulus. This is the same string shown in most browser's certificate information dialog boxes, but without spaces. For example:

```
"010001"
```

**signatureAlgorithm**: String (version 4.1.22459+)

The algorithm used to sign the certificate. Some possible values are:

- From RFC 3279:
  - md2WithRSAEncryption
  - md5WithRSAEncryption
  - sha1WithRSAEncryption
- From RFC 4055:
  - sha224WithRSAEncryption
  - sha256WithRSAEncryption
  - sha384WithRSAEncryption
  - sha512WithRSAEncryption
- From RFC 4491:
  - id-GostR3411-94-with-Gost3410-94
  - id-GostR3411-94-with-Gost3410-2001

**subject:** String  
The certificate subject CN string.

**cipherSuite:** String  
String representing the cryptographic cipher suite negotiated between the server and the client.

**clientExtensions:** Array (SSL\_OPEN and SSL\_RENEGOTIATE only)  
An array of extension objects. Each object has the following properties:

**id:** Number  
The ID number of the SSL extension

**name:** String  
The name of the SSL extension, if known. Otherwise "unknown" will be used.

**Known SSL Extensions**

ID	Name
0	server_name
1	max_fragment_length
2	client_certificate_url
3	trusted_ca_keys
4	truncated_hmac
5	status_request
6	user_mapping
7	client_authz
8	server_authz
9	cert_type
10	elliptic_curves
11	ec_point_formats
12	srp
13	signature_algorithms
14	use_srtp

ID	Name
15	heartbeat
16	application_layer_protocol_negotiation
17	status_request_v2
18	signed_certificate_timestamp
19	client_certificate_type
20	server_certificate_type
35	SessionTicket TLS
65281	renegotiation_info

**clientSessionId:** String  
The client session ID, byte array encoded as a string.

**contentType:** String (SSL\_RECORD only)  
The content type for the current record.

**handshakeTime:** Number (SSL\_OPEN and SSL\_RENEGOTIATE only)  
The amount of time required to negotiate the SSL connection, expressed in milliseconds. This is the amount of time between the client sending ClientHello and the server sending ChangeCipherSpec.

**HEARTBEAT\_TYPE\_REQUEST:** Number  
The heartbeatType is a request as specified in RFC 6520.

**HEARTBEAT\_TYPE\_RESPONSE:** Number  
The heartbeatType is a response as specified in RFC 6520.

**HEARTBEAT\_TYPE\_UNKNOWN:** Number  
A heartbeatType that is unknown because the connection was not decrypted.

**heartbeatPayloadLength:** Number (SSL\_HEARTBEAT only)  
The payload\_length field of the HeartbeatMessage data structure as specified in RFC 6520.

**heartbeatType:** Number (SSL\_HEARTBEAT only)  
The HeartbeatMessageType field of the HeartbeatMessage data structure as specified in RFC 6520.

**host:** string (SSL\_OPEN and SSL\_RENEGOTIATE only)  
The value of the SSL Server Name Indication (SNI), if present.

**isAborted:** Boolean (SSL\_CLOSE only)  
Returns true if the SSL session is aborted.

**isCompressed:** Boolean  
Returns true if the SSL record is compressed.

**isV2ClientHello:** Boolean  
Returns true if the Hello record corresponds to SSLv2.

**privateKeyId:** String  
Returns null if the ExtraHop appliance is not decrypting the SSL traffic. Returns a string ID associated with the private key if the ExtraHop appliance is decrypting the SSL traffic.

To find the private key ID in the ExtraHop Admin UI, go to the **Configuration** section, click **Capture**, click **SSL Decryption**, and then click a certificate. The pop-up window displays all identifiers for the certificate.

**record:** Object (SSL\_ALERT, SSL\_CLOSE, SSL\_HEARTBEAT, and SSL\_OPEN only)(version 5.0.0)  
Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

SSL_ALERT	SSL_CLOSE	SSL_HEARTBEAT	SSL_OPEN
alertCode	certificate.fingerprint	certificate.fingerprint	certificate.fingerprint
alertLevel	certificate.keySize	certificate.keySize	certificate.keySize
certificate.fingerprint	certificate.notAfter	certificate.notAfter	certificate.notAfter
certificate.keySize	certificate.signatureAlgorithm	certificate.signatureAlgorithm	certificate.signatureAlgorithm
certificate.notAfter	certificate.subject	certificate.subject	certificate.subject
certificate.signatureAlgorithm	cipherSuite	cipherSuite	cipherSuite
certificate.subject	isAborted	heartbeatPayloadLength	handshakeTime
cipherSuite	isCompressed	heartbeatType	host
isCompressed	version	isCompressed	isCompressed
version		version	version

**recordLength:** Number (SSL\_RECORD, SSL\_ALERT, and SSL\_HEARTBEAT only)  
The length field of the TLSPlaintext, TLSCompressed, and TLSCiphertext data structures as specified in RFC 5246.

**recordType:** Number (SSL\_RECORD, SSL\_ALERT, and SSL\_HEARTBEAT only)  
The type of field in the TLSPlaintext, TLSCompressed, and TLSCiphertext data structures as specified in RFC 5246.

**reqBytes:** Number (SSL\_RECORD and SSL\_CLOSE only)  
The number of request bytes.

**reqL2Bytes:** Number (SSL\_RECORD and SSL\_CLOSE only)  
The number of L2 request bytes.

**reqPkts:** Number (SSL\_RECORD and SSL\_CLOSE only)  
The number of request packets.

**rspBytes:** Number (SSL\_RECORD and SSL\_CLOSE only)  
The number of response bytes.

**rspL2Bytes:** Number (SSL\_RECORD and SSL\_CLOSE only)  
The number of L2 response bytes.

**rspPkts:** Number (SSL\_RECORD and SSL\_CLOSE only)  
The number of response packets.

**roundTripTime:** Number (SSL\_RECORD and SSL\_CLOSE only)  
The median round-trip time (RTT), expressed in milliseconds. Will return NaN if there are no RTT samples.

**serverExtensions:** Array (SSL\_OPEN and SSL\_RENEGOTIATE only)

An array of extension objects. Each object has the following properties:

**id:** Number

The ID number of the SSL extension

**name:** String

The name of the SSL extension, if known. Otherwise "unknown" will be used. See `clientExtensions` above for a list of known extension names.

**serverSessionId:** String

The server session ID, byte array encoded as a string.

**version:** Number

The SSL protocol version with the RFC hexadecimal version number expressed as a decimal.

Version	Hex	Decimal
SSLv3	0x300	768
TLS 1.0	0x301	769
TLS 1.1	0x302	770
TLS 1.2	0x303	771

## Telnet

The Telnet class allows retrieval of metrics available during the `TELNET_MESSAGE` event.

*Go to [Classes and Events](#).*

## Events

### TELNET\_MESSAGE

Fires on a telnet command or line of data from the telnet client or server.

*Go to [Classes and Events](#).*

## Methods

**commitRecord():** void (version 5.0.0)

Commits the record to the ExtraHop Explore appliance.

See the table under the **record** property below for details.

For built-in records, each unique record will be committed only once, even if `.commitRecord` is called multiple times for the same unique record.

## Properties

**command:** String

The command type. Will be null if the event fired due to a line of data being sent.

The possible values returned are:

- Abort
- Abort Output
- Are You There
- Break
- Data Mark
- DO
- DON'T
- End of File
- End of Record
- Erase Character
- Erase Line
- Go Ahead
- Interrupt Process
- NOP
- SB
- SE
- Suspend
- WILL
- WON'T

**line:** String

A line of the data sent by the client or server. Terminal escape sequences and special characters are filtered out. Things like cursor movement/line editing are not currently simulated (with the exception of backspace characters).

**option:** String

The option being negotiated. Will be null if the command is not an option command.

The possible values are:

- 3270-REGIME
- AARD
- ATCP
- AUTHENTICATION
- BM
- CHARSET
- COM-PORT-OPTION
- DET
- ECHO
- ENCRYPT
- END-OF-RECORD
- ENVIRON
- EXPOPL
- EXTEND-ASCII
- FORWARD-X
- GMCP
- KERMIT
- LINEMODE
- LOGOUT
- NAOCR D
- NAOFFD
- NAOHTD
- NAOHTS
- NAOL
- NAOLFD
- NAOP
- NAOVTD
- NAOVTS
- NAWS
- NEW-ENVIRON
- OUTMRK
- PRAGMA-HEARTBEAT
- PRAGMA-LOGON
- RCTE
- RECONNECT
- REMOTE-SERIAL-PORT
- SEND-LOCATION
- SEND-URL
- SSPI-LOGON
- STATUS
- SUPDUP
- SUPDUP-OUTPUT
- SUPPRESS-GO-AHEAD
- TERMINAL-SPEED
- TERMINAL-TYPE
- TIMING-MARK
- TN3270E
- TOGGLE-FLOW-CONTROL
- TRANSMIT-BINARY
- TTYLOC
- TUID



- X-DISPLAY-LOCATION
- X.3-PAD
- XAUTH

**optionData:Buffer**

For option subnegotiations (the "SB" command), the raw, option-specific data sent. Will be null if the command is not "SB".

**record:** Object (version 5.0.0)

Returns an object with all properties appropriately initialized. The event that this is called from determines the content of object returned.

The following table shows the properties available for the record of each event.

TELNET_MESSAGE
command
option

## Topnset

The Topnset class is used to represent topnset metrics. A topnset metric contains a list of entries with keys and values. Values may be numbers, **Dataset**, **Sampleset**, or even other Topnsets. **Topnset Keys** are objects that represent a property of Topnset.

*Go to **Classes and Events**.*

### Methods

**findEntries**(keyPattern: Object): Array  
Returns all entries with matching keys.

**findKeys**(keyPattern: Object): Array  
Returns all keys matching the specified pattern.

**lookup**(keyPattern: Object): \*  
Look up an item in the topnset, returning the first that matches the pattern.

### Properties

**entries**: Array  
An array of the topnset entries. The array contains  $N$  objects with key and value properties, with  $N$  currently being set to 1000.

## Topnset Keys

Topnset Keys are objects that represent a property of **Topnset**.

*Go to [Classes and Events](#).*

### Properties

**type:** String

The type of the topnset key. Possibilities include:

- string
- int
- ipaddr
- ether
- device\_id

**value:** \*

Varies depending on the type of key.

- For string keys, the value is a string.
- For int keys, the value is a number.
- For ipaddr keys, the value is an object containing:
  - addr
  - proto
  - port
  - device\_oid
  - origin
  - custom\_devices
- For ether keys, the value is an object containing:
  - ethertype
  - hwaddr

## TroubleGroup

In ExtraHop 4.0, it is possible to create your own trouble group. A trouble group is a set of devices for which a potential problem has been identified. This class may be used in conjunction with metric and discovery events (`NEW_DEVICE`, `METRIC_CYCLE_BEGIN`, `METRIC_RECORD_COMMIT`) to identify potential performances, security or configuration problems.

*Go to [Classes and Events](#).*

### Methods

**addDevice**(troubleGroupName: String, device: Device): void  
Adds a device to the specified trouble group.

### See Also

- **Example: Create a Custom Trouble Group**

## Turn

Turn is top-level object available in the `FLOW_TURN` event.

[Go to \*Classes and Events\*.](#)

### Properties

**clientBytes:** Number (version 4.0.20256+)

The size of the request that the client transferred, expressed in bytes.

**clientTransferTime:** Number (version 4.0.20256+)

The request transfer time, expressed in milliseconds. Corresponds to the **Network In** metric in the ExtraHop Web UI.

**processingTime:** Number (version 4.0.20256+)

The time elapsed between the client having transferred the request to the server and the server beginning to transfer the response back to the client, expressed in milliseconds. Corresponds to the **Processing Time** metric in the **Turn Timing** sections of the ExtraHop Web UI.

**serverBytes:** Number (version 4.0.20256+)

The size of the response that the server transferred, expressed in bytes.

**serverTransferTime:** Number (version 4.0.20256+)

The response transfer time, expressed in milliseconds. Corresponds to the **Network Out** metric in the ExtraHop Web UI.

**thinkTime:** Number (version 3.10.19576+)

The time elapsed between the server having transferred the response to the client and the client transferring a new request to the server, expressed in milliseconds. Will return NaN if there is no valid measurement.

### Deprecated

**reqSize:** Number (version 4.0.20256+)

Deprecated. Use `clientBytes` instead.

**reqXfer:** Number (version 4.0.20256+)

Deprecated. Use `clientTransferTime` instead.

**rspSize:** Number (version 4.0.20256+)

Deprecated. Use `serverBytes` instead.

**rspXfer:** Number (version 4.0.20256+)

Deprecated. Use `serverTransferTime` instead.

**tprocess:** Number (version 4.0.20256+)

Deprecated. Use `processingTime` instead.

## VLAN

The VLAN class represents a VLAN on the network.

Go to ***Classes and Events***.

### Properties

**id:** Number

The numerical ID of the VLAN.

## XML

Go to [Classes and Events](#).

Returns parsed XML data. Example:

```
var payload = "<Header><storeid>my_payload</storeid></Header>"
var xml = new XML(payload);
debug("storeid: " + xml.storeid); // The value is "my_payload."
```

## Examples

The following examples are available:

### **Example: HTTP Header Object**

Shows how to use the HTTP Headers object.

### **Example: SOAP Request**

Tracks SOAP requests via the SOAPAction header and stashes them into the flow store.

### **Example: Customer ID Header**

Records 500 errors by customer ID and URI.

### **Example: Database Trigger**

Records responses and processing time by database query.

### **Example: CIFS Trigger**

Records total read and written bytes as well as bytes written by users not authorized to access a sensitive resource.

### **Example: Memcache Hits and Misses**

Records keys for each hit or miss, and hit access time.

### **Example: Memcache Key Parsing**

Parses the memcache keys to extract detailed breakdowns by module and class name, as well as by ID.

### **Example: Trigger-Based Application Definition**

Creates an ExtraHop application container based on traffic associated with a two-tier application.

### **Example: Session Table**

Records specific transactions to the session table with operating system strings in HTTP.userAgent.

### **Example: Create a Custom Trouble Group**

Creates a custom trouble group.

### **Example: Topnset Key Matching**

Matches Topnset Keys.

### **Example: Use the Metric Cycle Store**

Illustrates the use of the Metric Cycle store.

### **Example: Device Discovery Notification**

Creates remote syslog messages when new devices are discovered.

### **Example: Parse Custom POS Messages with Universal Payload Analysis**

Parses a POS system custom TCP messages, looking for specific values in the 4th to 7th bytes of both response and request messages.

### **Example: Parse Syslog Over TCP with Universal Payload Analysis**

Parses the syslog over TCP and count the syslog activity over time, both network-wide and per device.

**Example: Send Data to ElasticSearch with Remote.HTTP**

Specify the JSON text suitable for ElasticSearch and send the information using Remote.HTTP

**Example: Send Information to Azure Table Service with Remote.HTTP**

Sends information to the Microsoft Azure Table Service via Remote.HTTP.

**Example: Active MQ**



## Example: HTTP Header Object

```
/*
 * Trigger: HTTP Headers Example
 * Description: Shows how to use the HTTP Headers object
 * Event: HTTP_RESPONSE
 */
var hdr,
    session,
    accept,
    results,
    headers = HTTP.headers,
    i;

/* Header lookups are case-insensitive properties */
session = headers["X-Session-Id"];

/*
 * session is a string representing the value of the header (or null,
 * if the header was not present). header values are always strings,
 * even for headers that typically have numbers as values.
 */

/* This syntax works too, if the header is a legal property name */
accept = headers.accept;
/*
 * In the event that there are multiple instances of a header,
 * accessing the header in the above manner (as a property)
 * will always return the value for the first appearance of the
 * header.
 */
if (session !== null)
{
    /* Count requests per session ID */
    Device.metricAddCount("req_count", 1);
    Device.metricAddDetailCount("req_count", session, 1);
}

/*
 * Looping over all headers
 *
 * "length" is a special property (case-sensitive) that is not
 * treated as a header lookup, but instead returns the number of
 * headers (as if HTTP.headers were an array). in the unlikely
 * event that there is a header called "Length," it would still be
 * accessible with HTTP.headers["Length"] (or HTTP.headers.Length).
 */
for (i = 0; i < headers.length; i++) {
    hdr = headers[i];
}
```

```
debug("headers[" + i + "].name: " + hdr.name);
debug("headers[" + i + "].value: " + hdr.value);
Device.metricAddCount("hdr_count", 1);
/* Count instances of each header */
Device.metricAddDetailCount("hdr_count", hdr.name, 1);
}

/* Searching for headers by prefix */
results = HTTP.findHeaders("Content-");

/*
 * result is an array (a real javascript array, as opposed to
 * an array-like object) of header objects (with name and value
 * properties) where the names match the prefix of the string passed
 * to findHeaders.
 */
for (i = 0; i < results.length; i++) {
    hdr = results[i];
    debug("results[" + i + "].name: " + hdr.name);
    debug("results[" + i + "].value: " + hdr.value);
}
```

#### See Also

- [Device](#)
- [HTTP](#)

## Example: SOAP Request

```
/*
 * Name: SOAP Action
 * Description: Tracks SOAP requests via the SOAPAction header and stashes them
 * into the flow store. The big requirement is that the SOAP implementation
 * actually passes this information. Not all do, so be sure and confirm that
 * part.
 * Events: HTTP_REQUEST, HTTP_RESPONSE
 */
var soapAction,
    headers = HTTP.headers,
    method,
    detailMethod,
    parts;

if (event === "HTTP_REQUEST") {
    soapAction = headers["SOAPAction"]
    if (soapAction != null) {
        Flow.store.soapAction = soapAction;
    }
}
else if (event === "HTTP_RESPONSE") {
    soapAction = Flow.store.soapAction;
    if (soapAction != null) {
        parts = soapAction.split("/");
        if (parts.length > 0) {
            method = soapAction.split("/") [1];
        }
        else {
            method = soapAction;
        }
        detailMethod = method + "_detail";
        Network.metricAddCount(method, 1);
        Network.metricAddDetailCount(detailMethod, Flow.client.ipaddr, 1);
        Network.metricAddSampleset("soap_proc", HTTP.tprocess);
        Network.metricAddDetailSampleset("soap_proc_detail", method,
            HTTP.tprocess);
    }
}
}
```

### See Also

- **FLOW**
- **HTTP**
- **Network**

## Example: Customer ID Header

```
/*
 * Name: Customer ID
 * Description: Record 500 errors by customer ID and URI.
 * Event: HTTP_REQUEST
 */
var custId,
    query,
    uri,
    key;

if (event === "HTTP_REQUEST") {
    custId = HTTP.headers["Cust-ID"];
    /* Only keep the URI if there is a customer id */
    if (custId !== null) {
        Flow.store.custId = custId;

        query = HTTP.query;

        /*
         * Pull the complete URI (URI plus query string) and record it on
         * the Flow store for a subsequent response event.
         *
         * The query string data is only available on the request.
         */
        uri = HTTP.uri;
        if ((uri !== null) && (query !== null)) {
            uri = uri + "?" + query;
        }

        /* Keep URIs for handling by HTTP_RESPONSE triggers */
        Flow.store.uri = uri;
    }
}
else if (event === "HTTP_RESPONSE")
{
    /*
     * Name: HTTP Cust-ID 500 URI Tracking
     * Comment: Record 500 errors by Customer ID and URI.
     * Event: HTTP_RESPONSE
     */
    custId = Flow.store.custId;

    /* Count total requests by customer ID */
    Device.metricAddCount("custid_rsp_count", 1);
    Device.metricAddDetailCount("custid_rsp_count_detail", custId, 1);

    /* If the status code is 500 or 503, record the URI and customer ID */
    if ((HTTP.statusCode === 500) || (HTTP.statusCode === 503))
```

```
{  
    /* combine URI and customer ID to create the detail key */  
    key = custId;  
    if (Flow.store.uri != null) {  
        key += ", " + Flow.store.uri;  
    }  
    Device.metricAddCount("custid_error_count", 1);  
    Device.metricAddDetailCount("custid_error_count_detail", key, 1);  
}  
}
```

### See Also

- **Device**
- **FLOW**
- **HTTP**

## Example: Database Trigger

```
/*
 * Name: DB Full Statement
 * Description: Record responses and processing times by database query
 * Events: DB_REQUEST, DB_RESPONSE
 *
 * Note: Assign this trigger to all the devices in a group and then
 * create a custom page for the Capture that displays the Network metric
 * to show the counts across the device group.
 */
var stmt = Flow.store.stmt;

if (event === "DB_REQUEST")
{
    /* Store the statement for the response. */
    Flow.store.stmt = DB.statement || DB.procedure;
    return;
}
if ((typeof stmt === "undefined") || (stmt === null))
{
    /*
     * Restrict statement length to 1024 bytes, since statements larger than
     * this are unlikely to be useful.
     */
    if (stmt.length > 1024) {
        stmt = stmt.substr(0, 1023);
    }

    /* Remove common blank line from front of DB procedures */
    if ((stmt.length > 0) && (stmt[0] === "\n")) {
        stmt = stmt.slice(1);
    }

    /* Record counts by statement */
    Device.metricAddCount("db_rsp_count", 1);
    Device.metricAddDetailCount("db_rsp_count_detail", stmt, 1);
    /* Record processing times by statement */
    Device.metricAddSampleset("db_proc_time", DB.tprocess);
    Device.metricAddDetailSampleset("db_proc_time_detail",
        stmt, DB.tprocess);

    /* Record these metrics at the network level as well */
    Network.metricAddCount("db_rsp_count", 1);
    Network.metricAddDetailCount("db_rsp_count_detail", stmt, 1);
    Network.metricAddSampleset("db_proc_time", DB.tprocess);
    Network.metricAddDetailSampleset("db_proc_time_detail",
        stmt, DB.tprocess);
}
```

### See Also

- **DB**
- **Device**
- **FLOW**
- **Network**

## Example: CIFS Trigger

```
/*
 * Name: CIFS Audit Support
 * Description: Records total read and written bytes as well as
 * bytes written by users not authorized to access a sensitive resource.
 * Event: CIFS_RESPONSE
 */
var client = Flow.client.device,
    server = Flow.server.device,
    clientAddress = Flow.client.ipaddr,
    serverAddress = Flow.server.ipaddr,
    file = CIFS.resource,
    user = CIFS.user,
    resource,
    permissions,
    writeBytes,
    readBytes;

/* Resource to monitor */
resource = "\\Clients\\Confidential\\";
/* Users of interest and their permissions */
permissions = {
    "\\EXTRAHOP\tom" : {read: false, write: false},
    "\\Anonymous" : {read: true, write: false},
    "\\WORKGROU\tbob" : {read: true, write: true}
};

/* Check if this is an action on our monitored resource */
if ((file !== null) && (file.indexOf(resource) !== -1)) {
    if (CIFS.isCommandWrite) {
        writeBytes = CIFS.reqSize;
        /* Record bytes written */
        Device.metricAddCount("cifs_write_bytes", writeBytes);
        Device.metricAddDetailCount("cifs_write_bytes", user, writeBytes);

        /* Record number of writes */
        Device.metricAddCount("cifs_writes", 1);
        Device.metricAddDetailCount("cifs_writes", user, 1);
        /* Record number of unauthorized writes */
        if (!permissions[user] || !permissions[user].write) {
            Device.metricAddCount("cifs_unauth_writes", 1);
            Device.metricAddDetailCount("cifs_unauth_writes", user, 1);
        }
    }

    if (CIFS.isCommandRead) {
        readBytes = CIFS.reqSize;
        /* Record bytes read */
        Device.metricAddCount("cifs_read_bytes", readBytes);
    }
}
```



```
Device.metricAddDetailCount("cifs_read_bytes", user, readBytes);
/* Record number of reads */
Device.metricAddCount("cifs_reads", 1);
Device.metricAddDetailCount("cifs_reads", user, 1);

/* Record number of unauthorized reads */
if (!permissions[user] || !permissions[user].read) {
    Device.metricAddCount("cifs_unauth_reads", 1);
    Device.metricAddDetailCount("cifs_unauth_reads", user, 1);
}
}
```

### See Also

- **CIFS**
- **Device**
- **FLOW**

## Example: Memcache Hits and Misses

```
/*
 * Name: Memcache_hits_misses
 * Description: Records keys for each hit or miss, and hit access time.
 * Event: MEMCACHE_RESPONSE
 */
var hits = Memcache.hits;
var misses = Memcache.misses;
var accessTime = Memcache.accessTime;
var i;

Device.metricAddCount('memcache_key_hit', hits.length);

for (i = 0; i < hits.length; i++) {
    var hit = hits[i];
    if (hit.key != null) {
        Device.metricAddDetailCount('memcache_key_hit_detail', hit.key, 1);
    }
}

if (!isNaN(accessTime)) {
    Device.metricAddSampleSet('memcache_key_hit', accessTime);
    if ((hits.length > 0) && (hits[0].key != null)) {
        Device.metricAddDetailSampleSet('memcache_key_hit_detail', hits[0].key,
            accessTime);
    }
}

Device.metricAddCount('memcache_key_miss', misses.length);

for (i = 0; i < misses.length; i++) {
    var miss = misses[i];
    if (miss.key != null) {
        Device.metricAddDetailCount('memcache_key_miss_detail', miss.key, 1);
    }
}
```

### See Also

- [Device](#)
- [Memcache](#)

## Example: Memcache Key Parsing

```
/*
 * Name: Memcache_Example_Trigger
 * Description: Parses the memcache keys to extract detailed breakdowns. Keys
 * look like:
 *     "com.extrahop.<module>.<class>_<id>"
 *     (for example: "com.extrahop.widgets.sprocket_12345")
 * and we want breakdowns by module and class name as well as ID.
 * Event: MEMCACHE_RESPONSE
 */

var method = Memcache.method;
var statusCode = Memcache.statusCode;
var reqKeys = Memcache.reqKeys;
var hits = Memcache.hits;
var misses = Memcache.misses;
var error = Memcache.error;
var hit;
var miss;
var key;
var size;
var reqKey;
var i;

/* Record breakdown of hit count and value size by module and class: */
for (i = 0; i < hits.length; i++) {
    hit = hits[i];
    key = hit.key;
    size = hit.size;

    Device.metricAddCount("hit", 1);
    if (key != null) {
        var parts = key.split(".");

        if ((parts.length == 4) && (parts[0] == "com") &&
            (parts[1] == "extrahop")) {
            var module = parts[2];
            var subparts = parts[3].split("_");

            Device.metricAddDetailCount("hit_module", module, 1);
            Device.metricAddDetailSampleset("hit_module_size", module, size);

            if (subparts.length == 2) {
                var hitClass = module + "." + subparts[0];

                Device.metricAddDetailCount("hit_class", hitClass, 1);
                Device.metricAddDetailSampleset("hit_class_size", hitClass,
                    size);
            }
        }
    }
}
```

```
    }
  }
}

/*
 * Users have reported slowness accessing sprockets. Record misses by ID to help
 * identify caching issues:
 */
for (i = 0; i < misses.length; i++) {
  miss = misses[i];
  key = miss.key;
  if (key != null) {
    var parts = key.split(".");

    if ((parts.length == 4) && (parts[0] == "com") &&
        (parts[1] == "extrahop") && (parts[2] == "widgets")) {
      var subparts = parts[3].split("_");

      if ((subparts.length == 2) && (subparts[0] == "sprocket")) {
        Device.metricAddDetailCount("sprocket_miss_id", subparts[1], 1);
      }
    }
  }
}

/* Record the key(s) that produced any errors: */
if (error != null && method != null) {
  for (i = 0; i < reqKeys.length; i++) {
    reqKey = reqKeys[i];
    if (reqKey != null) {
      var errDetail = method + " " + reqKey + " / " + statusCode + ": " +
        error;
      Device.metricAddDetailCount("error_key", errDetail, 1);
    }
  }
}

/* Record the status code, matching built-in metrics */
if (Memcache.isBinaryProtocol && statusCode != "NO_ERROR") {
  Device.metricAddDetailCount("status_code",
    method + "/" + statusCode,
    1);
}
else {
  Device.metricAddDetailCount("status_code", statusCode, 1);
}
```

### See Also

- **Device**
- **Memcache**

## Example: Trigger-Based Application Definition

```
/*
 * Name: Application Builder - My App
 * Description: Trigger to create an ExtraHop application container based
 *             on traffic associated with a two-tier application
 * Events: HTTP_RESPONSE, DB_RESPONSE
 * Assignments: All HTTP servers that process application HTTP traffic
 *             All DB servers that process application DB traffic
 * Firmware: 3.9+ required, 3.10+ recommended
 */

// Initialize the Application object against which we'll
// commit specific HTTP and DB transactions. After traffic is
// committed, an application container "My App" will appear in the
// Applications tab in the WebUI.
var myApp = Application("My App");
// These configurable properties describe features that define
// our application traffic.

var myAppHTTPHost = "myapp.internal.example.com";
var myAppDatabaseName = "myappdb";

if (event == "HTTP_RESPONSE") {

    // HTTP transactions can be committed to an Application on
    // HTTP_RESPONSE events.

    // Commit this HTTP transaction only if the HTTP Host header for
    // this response is defined and matches our application's HTTP Host.

    if (HTTP.host && (HTTP.host == myAppHTTPHost)) {

        myApp.commit();

        // Capture custom metrics about user agents that experience
        // HTTP 40x or 50x responses.

        if (HTTP.statusCode && (HTTP.statusCode >= 400))
        {

            // Increment the overall count of 40x or 50x responses
            myApp.metricAddCount('myapp_40x_50x', 1);

            // Collect additional detail on referer, if any

            if (HTTP.referer) {
                myApp.metricAddDetailCount('myapp_40x_50x_refer_detail',
                    HTTP.referer, 1);
            }
        }
    }
}
```

```
    }  
  
    }  
  
    } else if (event == "DB_RESPONSE") {  
        // Database transactions can be committed to an Application on  
        // DB_RESPONSE events.  
  
        // Commit this database transaction only if the database name for  
        // this response matches the name of our application database.  
        if (DB.database && (DB.database == myAppDatabaseName)) {  
            myApp.commit();  
        }  
    }  
}
```

### See Also

- **Application**
- **DB**
- **HTTP**

## Example: Session Table

```

/*
 * Name: Session Table
 * Description: Records specific transactions to the session table with operating
 * system strings in HTTP.userAgent.
 * Events: HTTP_REQUEST, SESSION_EXPIRE
 */

/* HTTP_REQUEST */
if (HTTP.userAgent === null) {
  return;
}

/* Look for the OS name */
var re = /(Windows|Mac|Linux)/;
var os = HTTP.userAgent.match(re);
if (os === null) {
  return;
}
/* Use matched string as key for session table entry */
os = os[0];

var opts =
{
  /* Expire added entries after 30 seconds */
  expire: 30,
  /* Retain entries with normal priority if the session table grows too large
 */
  priority: Session.PRIORITY_NORMAL,
  /* Make expired entries available on SESSION_EXPIRE events */
  notify: true
};
/* Ensure an entry for this key is present (an existing entry will not be
replaced) */
Session.add(os, 0, opts);
/* Increase the count for this entry */
var count = Session.increment(os);
debug(os + ": " + count);
After 30 seconds, the accumulated per-OS counts appear in the Session.expiredKeys
list, accessible in the SESSION_EXPIRE event:

/* SESSION_EXPIRE */
var keys = Session.expiredKeys;
for (var i = 0; i < keys.length; i++) {
  debug("count of " + keys[i].name + ": " + keys[i].value);
  if (keys[i].value > 500) {
    Network.metricAddCount("os-high-request-count", 1);
    Network.metricAddDetailCount("os-high-request-count",
      keys[i].name, 1);
  }
}

```



```
}  
}
```

#### See Also

- **HTTP**
- **Network**
- **Session**

## Example: Create a Custom Trouble Group

```
/*
 * Name: Create a Custom Trouble Group
 * Event: METRIC_RECORD_COMMIT
 * Advanced options: 30sec cycle, extrahop.device.http_server
 */
var fields = MetricRecord.fields,
    tprocess = fields.tprocess,
    slowWebServerThreshold = 200,
    pct1;

pct1 = tprocess.percentile(50);

if (pct1 > slowWebServerThreshold) {
    TroubleGroup.addDevice('Slow Web Servers', MetricRecord.object);
}
```

### See Also

- **MetricRecord**
- **TroubleGroup**

## Example: Topnset Key Matching

```
/*
 * Name: Topnset Key Matching
 * Event: METRIC_RECORD_COMMIT
 * Advanced options: 30sec cycle, extrahop.device.net_detail
 */
var stat = MetricRecord.fields['bytes_out'],
    entry,
    entries,
    key,
    i;

entries = stat.findEntries({addr: /192.168.112.1*/, proto: 17});

debug('matched ' + entries.length + '/' + stat.entries.length + ' entries');

for (i = 0; i < entries.length; i++) {
    entry = entries[i];
    key = entry.key;
    Remote.Syslog.alert('unexpected outbound UDP traffic from: ' +
        JSON.stringify(key));
}
```

### See Also

- [MetricRecord](#)
- [Remote.Syslog](#)

## Example: Use the Metric Cycle Store

```
/*
 * Name: Using the Metric Cycle Store
 * Event: METRIC_CYCLE_BEGIN, METRIC_RECORD_COMMIT, METRIC_CYCLE_END
 * Advanced options: 30sec cycle, extrahop.device.http_server, extrahop.device.tcp
 */
var store = MetricCycle.store;

function processMetric() {
    var id = MetricRecord.id,
        deviceId = MetricRecord.object.id,
        fields = MetricRecord.fields;

    if (!store.metrics[deviceId]) {
        store.metrics[deviceId] = {};
    }
    if (id === 'extrahop.device.http_server') {
        store.metrics[deviceId].httpRspAborted= fields['rsp_abort'];
    }
    else if (id === 'extrahop.device.tcp') {
        store.metrics[deviceId].tcpAborted = fields['aborted_out'];
    }
}

function commitSyntheticMetrics() {
    var dev,
        metrics,
        abortPct,
        deviceId;

    for (deviceId in store.metrics) {
        metrics = store.metrics[deviceId];
        abortPct = (metrics.httpRspAborted / metrics.tcpAborted) * 100;
        dev = new Device(deviceId);
        dev.metricAddSnap('http-tcp-abort-pct', abortPct);
    }
}

switch (event) {
case 'METRIC_CYCLE_BEGIN':
    store.metrics = {};
    break;

case 'METRIC_RECORD_COMMIT':
    processMetric();
    break;

case 'METRIC_CYCLE_END':
    commitSyntheticMetrics();
}
```

```
break;  
}
```

### See Also

- **Device**
- **MetricCycle**
- **MetricRecord**

## Example: Device Discovery Notification

```
/*
 * Name: Device Discovery Notification
 * Event: NEW_DEVICE
 */
var dev = Discover.device;
Remote.Syslog.info('Discovered device ' + dev.id + ' (hwaddr: ' + dev.hwaddr + ')
');
```

### See Also

- [Device](#)
- [Discover](#)
- [Remote.Syslog](#)

## Example: Parse Custom POS Messages with Universal Payload Analysis

Pare

```
/* Name: Parse Custom POS Messages with Universal Payload Analysis
 * Description: Parses a POS system custom TCP messages, looking for specific
 values
 *
 * in the 4th to 7th bytes of both response and request messages.
 * Event: TCP_PAYLOAD
 * Version: 4.1.24080
 */

//
// Define variables, store client or server payload into Buffer
//

var buf_client      = Flow.client.payload,
    buf_server      = Flow.server.payload,
    protocol         = Flow.l7proto,

//
// PoS Message Type Structure Definition
//
pos_message_type = {
    "0100" : "0100_Authorization_Request",
    "0101" : "0101_Authorization_Request_Repeat",
    "0110" : "0110_Authorization_Response",
    "0200" : "0200_Financial_Request",
    "0201" : "0201_Financial_Request_Repeat",
    "0210" : "0210_Financial_Response",
    "0220" : "0220_Financial_Transaction_Advice_Request",
    "0221" : "0221_Financial_Transaction_Advice_Request_Repeat",
    "0230" : "0230_Financial_Transaction_Advice_Response",
```

```
"0420" : "0420_Reversal_Advice_Request",
"0421" : "0421_Reversal_Advice_Request_Repeat",
"0430" : "0430_Reversal_Advice_Response",
"0600" : "0600_Administration_Request",
"0601" : "0601_Administration_Request_Repeat",
"0610" : "0610_Administration_Response",
"0620" : "0620_Administration_Advice_Request",
"0621" : "0621_Administration_Advice_Request_Repeat",
"0630" : "0630_Administration_Advice_Response",
"0800" : "0800_Administration_Request",
"0801" : "0801_Administration_Request_Repeat",
"0810" : "0810_Administration_Response"
};

//
// Skip parsing if it's other protocol of no interest or there is no payload
//
if (protocol !== 'tcp:4015' || (buf_client === null && buf_server === null)) {
    //debug('Not interested protocol: ' + protocol);
    return;
} else {
    // Store the data into variables for future access since there is some payload
    to parse
    var client_ip      = Flow.client.ipaddr,
        server_ip     = Flow.server.ipaddr,
        client_port   = Flow.client.port,
        server_port   = Flow.server.port;
    //client           = new Device(Flow.client.device.id),
    //server           = new Device(Flow.server.device.id);
}

if (buf_client !== null && buf_client.length >= 7) {

    // This is a client payload
    var cli_msg_type = buf_client.slice(3,7).decode('utf-8');
    debug('Client: ' + client_ip + ":" + client_port + " Type: " + pos_message_type
[cli_msg_type]);
    Device.metricAddCount('UPA_Request', 1);
    Device.metricAddDetailCount('UPA_Request_by_Message', pos_message_type[cli_msg_
type], 1);
    Device.metricAddDetailCount('UPA_Request_by_Client', client_ip.toString(), 1);
} else if (buf_server !== null && buf_server.length >= 7) {

    // This is a server payload
    var srv_msg_type = buf_server.slice(3,7).decode('utf-8');
    debug('Server: ' + server_ip + " Client: " + client_ip + ":" + client_port + "
Type: " + pos_message_type[srv_msg_type]);
    Device.metricAddCount('UPA_Response', 1);
    Device.metricAddDetailCount('UPA_Response_by_Message', pos_message_type[srv_
```

```
msg_type], 1);
    Device.metricAddDetailCount('UPA_Response_by_Client', client_ip.toString(), 1);

} else {

    // No buffer captured situation
    //debug('Null or not enough buffer data');
    return;
}
```

#### See Also:

- **Device**
- **FLOW**

### Example: Parse Syslog Over TCP with Universal Payload Analysis

**NOTE:** The complete solution that includes this trigger code is available on the [ExtraHop forums](#).

```
/* Name: Parse Syslog over TCP via Universal Payload Analysis
 * Description: Parses the syslog over TCP and count the syslog activity
 *              over time, both network-wide and per device.
 * Event: TCP_PAYLOAD, UDP_PAYLOAD
 * Version: 4.0.22123
 *
 */

//
// Variables we need throughout (aka global)
//

var buffer          = Flow.client.payload,
    buffer_size     = Flow.client.payload.length + 1,
    client          = new Device(Flow.client.device.id),
    data_as_json    = { client_ip      : Flow.client.ipaddr.toString(),
                        client_port   : Flow.client.port.toString(),
                        server_ip     : Flow.server.ipaddr.toString(),
                        server_port   : Flow.server.port.toString(),
                        protocol      : 'syslog',
                        protocol_fields : {} },

    protocol        = Flow.l7proto,
    server          = new Device(Flow.server.device.id),
    syslog          = {},
    syslog_facility = {
        "0": "kern",
        "1": "user",
        "2": "mail",
        "3": "daemon",
```



```
    "4": "auth",
    "5": "syslog",
    "6": "lpr",
    "7": "news",
    "8": "uucp",
    "9": "clock_daemon",
    "10": "authpriv",
    "11": "ftp",
    "12": "ntp",
    "13": "log_audit",
    "14": "log_alert",
    "15": "cron",
    "16": "local0",
    "17": "local1",
    "18": "local2",
    "19": "local3",
    "20": "local4",
    "21": "local5",
    "22": "local6",
    "23": "local7",
  },
  syslog_priority = {
    "0": "emerg",
    "1": "alert",
    "2": "crit",
    "3": "err",
    "4": "warn",
    "5": "notice",
    "6": "info",
    "7": "debug",
  };

//
// Exit out early if not classified properly or no payload
//

if ( ( protocol != 'tcp:5141' ) || ( buffer === null ) ) {
  debug('Invalid protocol ' + protocol +
    ' or null buffer (' + buffer.unpack('z').join(' ') + ')');
  return;
}

//
// Get started parsing Syslog
//

var data = buffer.unpack('z');

// Separate the PRIO field from the rest of the message
var msg_part = data[0].split('>')[1].split(' ');
```

```
var prio_part = data[0].split('>')[0].split('<')[1];

// Decode the PRIO field into Syslog facility and priority
var raw_facility = parseInt(prio_part) >> 3;
var raw_priority = parseInt(prio_part) & 7;

syslog.facility = syslog_facility[raw_facility];
syslog.priority = syslog_priority[raw_priority];

// Timestamp and hostname are technically part of the HEADER field, but
// we are just treating the rest of the message as a <space> delimited
// string (which it is, the syslog protocol is very basic)
syslog.timestamp = msg_part.slice(0,3).join(' ');
syslog.hostname = msg_part[3];
syslog.message = msg_part.slice(4).join(' ');

// At the network level, keep counts of who is sending messages by
// both facility and priority
Network.metricAddCount('syslog:priority_' + syslog.priority, 1);
Network.metricAddDetailCount('syslog:priority_' +
                             syslog.priority + '_detail',
                             Flow.client.ipaddr, 1);
Network.metricAddCount('syslog:facility_' + syslog.facility, 1);
Network.metricAddDetailCount('syslog:facility_' +
                              syslog.facility + '_detail',
                              Flow.client.ipaddr, 1);

// Devices receiving messages keep a count of who sent those messages
// by facility and priority
server.metricAddCount('syslog:priority_' + syslog.priority, 1);
server.metricAddDetailCount('syslog:priority_' +
                             syslog.priority + '_detail',
                             Flow.client.ipaddr, 1);
server.metricAddCount('syslog:facility_' + syslog.facility, 1);
server.metricAddDetailCount('syslog:facility_' +
                              syslog.facility + '_detail',
                              Flow.client.ipaddr, 1);

// Devices sending messages keep a count of who they sent those messages
// to by facility and priority
client.metricAddCount('syslog:priority_' + syslog.priority, 1);
client.metricAddDetailCount('syslog:priority_' +
                             syslog.priority + '_detail',
                             Flow.server.ipaddr, 1);
client.metricAddCount('syslog:facility_' + syslog.facility, 1);
client.metricAddDetailCount('syslog:facility_' +
                              syslog.facility + '_detail',
                              Flow.server.ipaddr, 1);

data_as_json.protocol_fields = syslog;
```

```
data_as_json.ts          = new Date();

//try {
//    Remote.MongoDB.insert('payload.syslog', data_as_json);
//}
//catch ( err ) {
//    Remote.Syslog.debug(JSON.stringify(data_as_json));
//}
debug('Syslog data: ' + JSON.stringify(data_as_json, null, 4));"
```

#### See Also:

- **FLOW**
- **Network**
- **Remote.MongoDB**
- **Remote.Syslog**

#### Example: Send Data to Elasticsearch with Remote.HTTP

```
/*
 * Name: Send Data to Elasticsearch with Remote.HTTP
 * Description: Specify the JSON text suitable for Elasticsearch and
 *              send the information using Remote.HTTP
 * Version: 4.1.23251+
 */

var date = new Date();
var payload = {
    'ts' : date.toISOString(), // Timestamp recognized by
Elasticsearch
    'eh_event' : 'http',
    'my_path' : HTTP.path};
var obj = {
    'path' : '/extrahop/http', // Add to extrahop index
    'headers' : {},
    'payload' : JSON.stringify(payload) } ;

Remote.HTTP('elasticsearch').request('POST', obj);
```

#### See Also:

- **Remote.HTTP**

#### Example: Send Information to Azure Table Service with Remote.HTTP

**Note:** This example requires the configuration of Open Datastream for HTTP to use Microsoft Azure request signing.

```
/*
 * Name: Send Information to Azure Table Service with Remote.HTTP
 * Description: Sends information to the Microsoft Azure Table Service via
Remote.HTTP.
 * Version: 4.1.23251+
 */

// the name of the HTTP destination defined in the ODS config
var REST_DEST = "my_table_storage";

// the name of the table within Azure Table Storage
var TABLE_NAME = "TestTable";

/* If the header is not set to this value, Azure Table Storage
 * expects to receive XML; however, it is easier for a trigger to
 * send JSON. The odata information enables you to specify the
 * datatype of fields; in this case TS is a datetime even though
 * it is serialized from a Date to a String.
 */

var headers = { "Content-Type": "application/json;odata=minimalmetadata" };

var now = new Date(getTimestamp());
var msg = {
    "RowKey":      now.getTime().toString(), // must be a string
    "PartitionKey": "my_key", // must be a string
    "HTTPMethod":  HTTP.method,
    "DestAddr":    Flow.server.ipaddr,
    "SrcAddr":     Flow.client.ipaddr,
    "SrcPort":     Flow.client.port,
    "DestPort":    Flow.server.port,
    "TS@odata.type": "Edm.DateTime", // metadata to describe format of TS field
    "TS":          now.toISOString(),
    "ServerTime":  HTTP.tprocess,
    "RspTTLB":     HTTP.rspTimeToLastByte,
    "RspCode":     HTTP.statusCode.toString(),
    "URI":         "http://" + HTTP.host + HTTP.path,
};

//debug(JSON.stringify(msg));
Remote.HTTP(REST_DEST).post( { path: "/" + TABLE_NAME, headers: headers, payload:
JSON.stringify(msg) } );
```

### See Also:

- **Remote.HTTP**

## Example: Active MQ

```
{code:javascript}
var app = Application("ActiveMQ Sample");
if (ActiveMQ.senderIsBroker) {
  if (ActiveMQ.receiverIsBroker) {
    app.metricAddCount("amq_broker", 1);
    app.metricAddDetailCount("amq_broker", ActiveMQ.queue, 1);
  }
  else {
    app.metricAddCount("amq_msg_out", 1);
    app.metricAddDetailCount("amq_msg_out", ActiveMQ.queue, 1);
  }
}
else {
  app.metricAddCount("amq_msg_in", 1);
  app.metricAddDetailCount("amq_msg_in", ActiveMQ.queue, 1);
}
{code}
```