Configure a threshold alert

Published: 2025-01-22

Configure a threshold alert to monitor when a specific metric crosses a defined boundary. For example, you can generate an alert when an HTTP 500 status code is observed more than 100 times during a ten minute period.

Before you begin

You must have full write privileges 🛛 or higher.

- 1. Log in to the ExtraHop system through https://<extrahop-hostname-or-IP-address>.
- 2. Click the System Settings icon 🏶 and then click Alerts.
- 3. Click Create.
- 4. Type a unique name for the alert configuration in the **Name** field.
- 5. In the **Description** field, add information about the alert.



Tip: Alert descriptions support Markdown, which is a simple formatting syntax that converts plain text into HTML. For more information, see the Alerts FAQ 2.

- 6. In the Alert Type section, click Threshold Alert.
- 7. In the **Assigned Sources** field, type the name of a device, device group, or application and then select from the search results.

To search for a site, flow network, or flow interface, select that source type from the drop-down menu at the top of the search results.

8. Optional: Click **Add Source** to assign the alert to multiple sources. Multiple sources must be of the same type, such as only devices and device groups or only applications.

Tip: Assign an alert to a device group to efficiently manage assignments to multiple devices.

9. In the **Monitored Metric** field, type the name of a metric and then select from the search results. The metric must be compatible with the assigned sources. For example, if you assign the alert to an application, you cannot select a device metric.



Note: If you select a detail metric , you can specify a key value. For example, you might select HTTP - Responses by Status Code and then specify 404 as the key value. An alert is generated only when HTTP responses with 404 status codes occur.

Monitored Metric		
HTTP - Responses by Status Code		×
Where Status Code matches	404	
		🗆 Ratio

10. Optional: To monitor the value of a metric divided by a secondary metric, click **Ratio** and then select a secondary metric.

For example, you can monitor the percentage of HTTP errors occurring on responses by dividing HTTP response errors by HTTP responses.

Monitored Metric	
HTTP Server - Errors	×
divide	l by
HTTP Server - Responses	×
	🗹 Ratio

11. In the Alert Condition section, specify conditions for generating an alert.

Metric 0	Calculation		Time Interval		
Alert Condition					
Alert when Cour	nt 🔻 is	≥ ▼	300	during a 5m	rollup 🔻
	Ope	rator	Metric Value		

a) Select a metric calculation to specify how to calculate the metric value within the time interval. The options available depend on the data type.

Count	Count		
	Rate per second		
	Rate per minute		
	Rate per hour		
Dataset	Minimum		
	25th percentile		
	Median		
	• 75th percentile		
	Maximum		
Sampleset	Mean		
	 +1 to +7 standard deviations 		
	-1 to -7 standard deviations		
Maximum, Snapshot	No measurement; the operator compares the actual metric value.		

- b) Select an operator to specify how to compare the metric calculation to the metric value.
- c) Specify the metric value to be compared to the metric calculation.
- d) Select the time interval over which the metric value is observed and metric data is aggregated, or rolled up. You can select a time interval from 30 seconds up to 30 minutes.

For example, to generate an alert when more than 300 HTTP response errors occur within 5 minutes, specify the following conditions:

- Metric Calculation: Count
- Operator: >
- Metric Value: 300
- Time Interval: 5m rollup
- 12. Optional: In the Notifications section, add an email notification to an alert 🛽 to receive emails or SNMP traps when an alert is generated.

- 13. In the Status section, click an option to enable or disable the alert.
- 14. Optional: Add an exclusion interval 🛛 to suppress alerts during specific times.
- 15. Click Save.