


Deploy the ExtraHop Command Appliance in AWS

Published: 2019-01-07

This guide explains how to launch the ExtraHop Command appliance AMI to monitor your Amazon Web Services (AWS) environment. You must have administrative access to AWS to launch a third-party AMI and an ExtraHop product key to complete these procedures.

Before you deploy the Command appliance, determine the optimal provisioning needs for your environment. For more information, see the [Performance guidelines](#) section.

 **Important:** If you want to deploy more than one ExtraHop virtual appliance, create the new instance with the original deployment package or clone an existing instance that has never been started.

Performance guidelines

The following table provides guidelines that can help you optimize the performance of the Command appliance. These guidelines are minimum requirements that you might need to adjust based on the size and needs of your environment.

| Scalability | Connected ExtraHop Appliances | 1-4 | 5-16 | 17-64 | 65 or more |
|---------------------------|-------------------------------|-------|-------|-------|------------|
| Provisioning Requirements | CPU Cores | 2 | 4 | 8 | 16 |
| | RAM | 4 GB | 8 GB | 16 GB | 24 GB |
| | Boot Disk | 4 GB | 4 GB | 4 GB | 4 GB |
| | Datastore Disk | 40 GB | 48 GB | 64 GB | 80 GB |
| | Disk Total | 44 GB | 52 GB | 68 GB | 84 GB |

Create the ExtraHop instance in AWS

Before you begin

The Amazon Machine Images (AMIs) of ExtraHop appliances are not publicly shared. Before you can start the deployment procedure, you must send your AWS account ID to support@extrahop.com. Your account ID will be linked to the ExtraHop AMIs.

1. Sign in to AWS with your username and password.
2. Click **EC2**.
3. In the left navigation panel, under Images, click **AMIs**.
4. Above the table of AMIs, change the **Filter** from **Owned by Me** to **Private Images**.
5. In the **Search AMIs...** field, type `ExtraHop`.
6. Select the checkbox next to the ExtraHop Command appliance AMI, and click **Launch**.
7. In the left navigation panel, click **General Purpose** and select **m3.large**.
8. Click **Next: Configure Instance Details**.
9. From the **Network** drop-down list, select **Launch into EC2-Classic** or select a **VPC**.

You must launch the Command appliance in the same environment as the ExtraHop Discover appliances.

10. Select **Stop** as the default shutdown behavior.
11. Click the **Protect against accidental termination** checkbox.
12. Optional: Click the **IAM role** drop-down list, and select an IAM role.
13. Optional: If you want to configure two interfaces for VPC, scroll down to the Network Interfaces section and click **Add Device** to associate another interface with your instance.
The default number of network interfaces is one. The two interfaces must be on two different subnets.
14. Click **Next: Add Storage**.
15. Accept the defaults and click **Next: Tag Instance**.
16. In the **Value** field, enter a name for the instance.
17. Click **Next: Configure Security Group**.
18. On the Configure Security Group page, follow the procedure below to create a new security group or add ports to an existing group. If you already have a security group with the required ports for ExtraHop, you can skip this step.

- a) Select either **Create a new Security Group** or **Select an existing security group**. If you choose to edit an existing group, select the group you want to edit. If you choose to create a new group, type a name for the Security group and type a **Description**.
- b) From the **Type** drop-down list, select a protocol. Type the port number in the Port Range field.
- c) For each additional port, click the **Add Rule** button. Then, from the **Type** drop-down list, select a protocol, and type the port number in the Port Range field.

The following ports and IP addresses must be opened for the ExtraHop AWS instance:

TCP ports 22, 80, and 443 inbound to the Command appliance

These ports must be open to download the installer and administer the ExtraHop system. If you cannot open port 80, you can copy the installer to each instance manually.

IP addresses of the ExtraHop Discover appliances that are connected to the Command appliance

After the Command appliance is launched, you must modify the security groups of the connected Discover appliances to allow traffic in from the Command appliance.

19. Click **Review and Launch**.
20. Scroll down to review the AMI details, instance type, and security group information, and then click **Launch**.
21. In the pop-up window, from the first drop-down list, select **Proceed without a key pair**.
22. Click the **I acknowledge...** checkbox and then click **Launch Instance**.
23. Click **View Instances** to return to the AWS Management Console.
When you return to the AWS Management Console, you can view your instance on the Initializing screen.

Located under the table, on the **Description** tab, is the IP address or hostname for the Command appliance.

Register an ExtraHop system in AWS

Complete the following steps to apply a product key supplied by ExtraHop Support in an AWS environment.

If you do not have a product key, contact your ExtraHop account team.



Tip: To verify that your environment can resolve DNS entries for the ExtraHop licensing server, open a terminal application on your Windows, Linux, or Mac OS client and run the following command:

```
nslookup -type=NS d.extrahop.com
```

If the name resolution is successful, output similar to the following appears:

```
Non-authoritative answer:  
d.extrahop.com nameserver = ns0.use.d.extrahop.com.  
d.extrahop.com nameserver = ns0.usw.d.extrahop.com.
```

1. In your browser, type the IP address of the ExtraHop appliance (`https://<extrahop_management_ip>`).
2. Review the license agreement, select **I Agree**, and click **Submit**.
3. On the log in screen, type `setup` for the user name and the instance ID for the password.
You can find the Instance ID on the Description tab of an instance selected on the Initializing screen.
Type the string of characters that follow `i-` (but not `i-` itself), and then click **Log In**.
4. Enter your product key, and then click **Register**.