


# Create an exclusion interval for alerts

Published: 2018-10-19

Exclusion intervals define a time in which alerts are suppressed. For example, if you do not want to be notified about alerts after hours or on the weekends, create an exclusion interval that specifies the time period to suppress alerts. After you create the exclusion interval, you can assign it to one or more alert configurations.


1. Log into the Web UI on the ExtraHop Discover or Command appliance.
2. Click the System Settings icon  and then click **Alerts**.
3. Click the **Exclusion Intervals** tab, and then click **New**.
4. Enter a unique name for the exclusion interval in the **Name** field.
5. Optional: In the Assign to All section, you can assign the exclusion interval to all alert configurations or only to trend alert configurations.
  - To assign the exclusion interval to all existing and future alert configurations, click **Alerts**.
  - To assign the exclusion interval to all existing and future trend alert configurations, click **Trend**.
6. From the Exclude section, specify one of the following time frame options for the exclusion interval:
  - To set a one-time exclusion interval, select **From**.
  - To set a daily exclusion interval, select **Every day**.
  - To set a weekly exclusion interval, select **Every week from**.
7. Click **OK**.

## Assign an exclusion interval to an alert

Assign one or more exclusion intervals to an alert configuration to suppress generation of alerts during a specified time frame.


### Before you begin

You must configure an alert before you assign an exclusion interval. See [Configure threshold alert settings](#), [Configure trend alert settings](#), or [Configure detection alert settings](#).

1. Log into the Web UI on the ExtraHop Discover or Command appliance.
2. Click the System Settings icon  and then click **Alerts**.
3. Click the alert configuration you want to open in the Alert Configuration window.
4. Click the **Exclusion Intervals** tab.
5. Select the checkbox next to each exclusion interval you want to assign to the alert.
6. Click **OK**.

## View the exclusion interval history

The exclusion interval history displays the last 100 changes made to exclusion interval configurations.

1. Log into the Web UI on the ExtraHop Discover or Command appliance.
2. Click the System Settings icon  and then click **Alerts**.
3. Click the **Exclusion Intervals** tab, and then click the **History** tab.  
The tab displays the following information:

### Change

Displays the change that was made to the exclusion interval.

**Author**

Displays the author of the change.

**Timestamp**

Displays when the change was made.

4. Click **OK** to close the window.