

# Triggers FAQ

---

Published: 2021-08-27

Here are some answers to frequently asked questions about triggers.

- [Where should I create a trigger if I have a Command appliance or Reveal\(x\) 360?](#)
- [How do I unassign a trigger?](#)
- [How do I disable or enable a trigger?](#)
- [Can I copy a trigger?](#)
- [Can I automatically indent trigger code?](#)

## Where should I create a trigger if I have a Command appliance or Reveal(x) 360?

Triggers can be created on individual ExtraHop systems or on Command appliances and Reveal(x) 360 that are connected to multiple ExtraHop systems. When you create a trigger on a Command appliance or Reveal(x) 360 system, the trigger runs on any connected system where the trigger event occurs.

## How do I unassign a trigger?

There are two methods for removing a trigger assignment:

- Open the device or group the trigger is assigned to and click **Assignments** from the top-right corner of the page. On the Triggers tab, click the remove (X) icon next to each trigger assignment you want to remove from the source.
- Open the trigger you want and click the **Assignments** tab to view which sources the trigger is assigned to. Click the remove (X) icon next to each device or device group you want to remove the trigger assignment from.


## How do I disable or enable a trigger?

There are two methods to enable or disable a trigger from the Triggers page in System Settings:

- From the list of triggers, select the checkbox next to each trigger, and then click **Enable** or **Disable** from the upper-right corner.
- Open the trigger you want, and then select or deselect **Disable Trigger**.

## Can I copy a trigger?

You can create a new trigger by copying an existing one.

1. Log in to the ExtraHop system through `https://<extrahop-hostname-or-IP-address>`.
2. Click the System Settings icon , and then click **Triggers**.
3. From the table on the Triggers page, select the checkbox next to the trigger that you want to copy.
4. Click **Copy**.

The copied trigger is added to the table with "(copy)" appended to the trigger name. By default, the copied trigger is not assigned to any devices or device groups.

## Can I automatically indent trigger code?

You can automatically indent code in the trigger editor by pressing ALT + SHIFT + F.