

Transfer management of analysis priorities


Published: 2025-01-10

Each packet sensor can manage its own analysis priorities, which determine which devices receive Advanced Analysis or Standard Analysis. If your sensor is connected to a console, you can transfer priority management to that console for a centralized view of these settings.

Here are some important considerations about transferring management:

- You must have full write privileges to edit analysis priorities.
- After management is transferred to a console, any further changes you make on individual sensors are inactive. See which other **settings are also transferred** [🔗](#).
- Analysis Priorities settings are not available for flow sensors; management cannot be transferred.

The following steps show you how to transfer priority management to a console:

1. Log in to the ExtraHop system.
Repeat these steps on each sensor in your environment.
2. Click the System Settings icon  and then click **Analysis Priorities**.
3. At the top of the page, click the Console drop-down menu and select the console that you want to transfer management to.
4. Click **Transfer**.



Tip: To avoid analysis disruptions, you can save a draft of the analysis priorities settings for each sensor before transferring management to a console.