

# Transfer management of analysis priorities


Published: 2022-03-19


By default, each sensor (Discover appliance) manages its own analysis priorities, which determine which devices receive Advanced Analysis or Standard Analysis. If your sensor is connected to a Command appliance or Reveal(x) 360, you can transfer priority management to one of those systems for a centralized view of these settings.

Here are some important considerations about transferring management:

- You must have full write privileges to edit analysis priorities.
- After management is transferred to a Command appliance or Reveal(x) 360 system, any further changes you make on individual sensors are inactive. See which other [settings are also transferred](#).
- Analysis Priorities settings are not available for flow sensors; management cannot be transferred.

The following steps show you how to transfer priority management:

1. Log in to the ExtraHop system.  
Repeat these steps on each sensor (Discover appliance) in your environment.
2. Click the System Settings icon  and then click **Analysis Priorities**.
3. At the top of the page, click the Appliance drop-down list and select the ExtraHop system that you want to transfer management to.
4. Click **Transfer**.

 **Tip:** To avoid analysis disruptions, you can save a draft of the analysis priorities settings for each ExtraHop system before transferring management to a Command appliance or Reveal(x) 360.

