

Deploy the ExtraHop Trace Appliance in Azure

Published: 2020-02-24

The following procedures explain how to deploy an ExtraHop Trace virtual appliance in a Microsoft Azure environment. You must have experience administering in an Azure environment to complete these procedures.

Before you begin

- You must have experience deploying virtual machines in Azure within your virtual network infrastructure. To ensure that the deployment is successful, make sure you have access to, or the ability to create the required resources. You might need to work with other experts in your organization to ensure that the necessary resources are available.
- You must have a Linux, Mac, or Windows client with the latest version of [Azure CLI](#) installed.
- You must have the ExtraHop virtual hard disk (VHD) file, available on the [ExtraHop Customer Portal](#).
- You must have an ExtraHop product key.

System requirements

The table below shows the environmental parameters that you need to configure, or might have already configured in your Azure environment to successfully deploy your ExtraHop virtual appliance.

Parameter	Description
Azure account	Provides access to your Azure subscriptions.
Resource Group	A container that holds related resources for the ExtraHop appliance.
Location	The geographic region where the Azure resources are located to sustain your virtual appliances.
Storage account	The Azure storage account contains all of your Azure Storage data objects, including blobs and disks.
Blob storage container	The storage container where the ExtraHop appliance image is stored as a blob.
Managed disk	The disk required for ExtraHop appliance data storage.
Network security group	The network security group contains security rules that allow or deny inbound network traffic to, or outbound network traffic from the ExtraHop appliance.
Azure VM instance size	An Azure instance size that most closely matches the Discover appliance VM size, as follows: <ul style="list-style-type: none"> • ETA 1150v: Standard_D4S_v3
Public or private IP address	The IP address that enables access to the Web UI and Admin UI of the ExtraHop appliance.

Deploy the ETA 1150v

Before you begin

The procedures below assume that you do not have the required resource group, storage account, storage container, and network security group configured. If you already have these parameters configured, you can proceed to step 6 after you log into your Azure account.

1. Open a terminal application on your client and log into to your Azure account.

```
az login
```

2. Open <https://aka.ms/devicelogin> in a web browser and enter the code to authenticate, and then return to the command-line interface.
3. Create a resource group.

```
az group create --name <name> --location <location>
```

For example, create a new resource group in the West US region.

```
az group create --name exampleRG --location westus
```

4. Create a storage account.

```
az storage account create --resource-group <resource group name> --name <storage account name>
```

For example:

```
az storage account create --resource-group exampleRG --name exampleSA
```

5. View the storage account key. The value for **key1** is required for step 5.

```
az storage account keys list --resource-group <resource group name> --account-name <storage account name>
```

For example:

```
az storage account keys list --resource-group exampleRG --account-name exampleSA
```

Output similar to the following appears:

```
[
  {
    "keyName": "key1",
    "permissions": "Full",
    "value": "CORuU8mTcxLxq0bbszhZ4RKTb93CqLpjZdAhCrNJugAorAyvJjhGmBSedjYPmzXPikSRigd5T5/YGYBoIzxNg=="
  },
  {
    "keyName": "key2",
    "permissions": "Full",
    "value": "D0lda4+6U3Cf5TUAng8/GKotfX1HHJuc3yljAlU+aktRAf4/KwVQUuAUhndrw2yg5Pba5FpZn6oZYvROncnT8Q=="
  }
]
```

6. Set default Azure storage account environment variables. You can have multiple storage accounts in your Azure subscription. To select one account to apply to all subsequent storage commands, set

these environment variables. If you do not set environment variables you will always have to specify `--account-name` and `--account-key` in the commands in the rest of this procedure.

```
export AZURE_STORAGE_ACCOUNT=<storage account_name>
```

```
export AZURE_STORAGE_KEY=<key1>
```

Where `<key1>` is the storage account key value that appears in step 5.

For example:

```
export AZURE_STORAGE_ACCOUNT=exampleSA
```

```
export AZURE_STORAGE_KEY=CORuU8mTcxLxq0bbszhZ4RKTb93CqLpjZdAhCrNJugAor
AyvJjhGmBSedjYPmzXPikSRigd5T5/YGYBoIzxNg==
```

7. Create a storage container.

```
az storage container create --name <storage container name>
```

For example:

```
az storage container create --name exampleSC
```

8. Upload the Trace appliance VHD file to the blob storage.

```
az storage blob upload --container-name <container> --type page --name
<blob name> --file <path/to/file> --validate-content
```

For example:

```
az storage blob upload --container-name exampleSC --type page
--name trace_appliance.vhd --file /Users/admin/Downloads/extrahop-eta-
azure-7.2.0.5000.vhd --validate-content
```

9. Retrieve the blob URI. You will need the URI when you create the managed disk in the next step.

```
az storage blob url --container-name <storage container name> --name
<blob name>
```

For example:

```
az storage blob url --container-name exampleSC --name trace_appliance.vhd
```

Output similar to the following example appears:

```
https://exampleSA.blob.core.windows.net/exampleSC/trace_appliance.vhd
```

10. Create a managed disk, sourcing the Trace VHD file.

```
az disk create --resource-group <resource group name> --location <Azure
region>
--name <disk name> --sku Premium_LRS --source <blob uri> --size-gb <size
gb>
```

Where `storage SKU` specifies the type of disk and desired replication pattern. For example, `Premium_LRS`, `StandardSSD_LRS`, or `Standard_LRS`.

You can configure the disk size (`--size-gb`) between 50 GB and 4 TB

For example:

```
az disk create --resource-group exampleRG --location westus
--name exampleDisk --sku Standard_LRS --source https://
exampleSA.blob.core.windows.net/exampleSC/trace_appliance.vhd
--size-gb 60
```

11. Create the VM and attach the managed disk. This command creates the Trace appliance VM with a default network security group and private IP address.

```
az vm create --resource-group <resource group name> --public-ip-address
""
--location <Azure region> --name <vm name> --os-type linux --attach-os-
disk <disk name>
--size <azure machine size>
```

For example:

```
az vm create --resource-group exampleRG --public-ip-address ""
--location westus --name exampleVM --os-type linux
--attach-os-disk exampleDisk --size Standard_D4S_v3
```

12. Log into the Azure portal, <https://portal.azure.com>, and configure the networking rules for the appliance. The network security group must have the following rules configured:

Table 1: Inbound Port Rules

Name	Port	Protocol
HTTPS	443	TCP
RPCAP	2003	TCP
RPCAP	2003-2034	UDP
SSH	22	TCP

Table 2: Outbound Port Rules

Name	Port	Protocol
HTTPS	443	TCP
RPCAP	2003	TCP
SSH	22	TCP

Next steps

Open a web browser and log into the Admin UI on the Trace appliance through the configured IP address. The default login name is **setup** and the password is **default**.

[Register your ExtraHop appliance](#) and complete the recommended procedures in the [post-deployment checklist](#).